




# Printing Guidelines - Photoshop CS5

Before you print


1. Confirm that your image is the correct resolution to print (300 ppi) at the physical size of your print. In the menu bar: **Image > Image Size**. Confirm that the height and width of your image are suited to the paper you plan to print on.




2. Confirm your Photoshop Color Settings are set to AdobeRGB (1998). In the menu bar: **Edit > Color Settings**.
  - a. Under **Working Spaces**, choose **AdobeRGB(1998)**.
  - b. Under **Color Management Policies**, choose **Convert to Working RGB**



3. In the **Print Dialog Box** (in the menu choose **File > Print**) -
- Confirm the Printer you intend to use is selected (Epson 3800, Epson 3880, Epson 2400, Epson 7600)




4. Confirm Color Management and Paper Profile settings
- Confirm that the **Document** is (**Profile: AdobeRGB(1998)**)
  - Color Handling: Photoshop Manages Colors**
  - Choose your paper profile - **Printer Profile: PLPP for Epson Luster / PGPP for Epson Glossy**  
For a complete list of Epson paper abbreviations look on the wall by the printers.




5. Set the proper paper size or establish a custom paper size -

a. Select the Print Settings tab





b. Select the paper size. If a custom size, select Manage Custom Sizes







- c. Click on the + to add a new size. Enter your paper size and margins to the right.
- d. In the list to the left, click on the new paper profile to rename it.
- e. After clicking OK, confirm that your new custom size is actually selected. If it isn't, it will be listed at the end of all the pre-set papers. Your custom paper settings will be saved for future use in your personal Photoshop preferences.
- f. Confirm that your image appears on the paper as you anticipated in the preview window.
- g. Adjust the position of the image on the paper if you like (default is centered)
- h. Ok / save back to the main Print Settings window.



6. Stay in the **Printer Settings** window
  - a. Twirl open the menu below the Paper Size.
  - b. Select the Printer Settings option
  - c. Confirm that the **Media Type** is correct - Premium Photo Paper Luster, etc.
  - d. **Printer Mode: AccuPhoto HD**
  - e. **Color Mode: Off No Color Management**
  - f. **Output Resolution: SuperPhoto 1440 dpi**
  - g. Deselect **High Speed**
  - h. Ok / Save back to the main print window.



The paper type should match your paper and the paper profile setting in the main window.

7. PRINT! Your paper should rest in the right side of the sheet feeder. Pull out the tray in the front of the printer to catch your print when it's done. Check the color of your print in natural light by the window - the fluorescents are deceptive.

**If the color is radically off, confirm you've chosen the proper color profile (eg AdobeRGB1998) and the proper type of paper. If either of those settings are incorrect, your image color will be off.**