hp 12c financial calculator

user's guide



HP Part Number 0012C-90001

File name: hp 12c_user's guide_English_HDPMBF12E44 Printed Date: 2005/7/29 Page: 1 of 209

Notice

REGISTER YOUR PRODUCT AT: www.register.hp.com

THIS MANUAL AND ANY EXAMPLES CONTAINED HEREIN ARE PROVIDED "AS IS" AND ARE SUBJECT TO CHANGE WITHOUT NOTICE. HEWLETT-PACKARD COMPANY MAKES NO WARRANTY OF ANY KIND WITH REGARD TO THIS MANUAL, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT AND FITNESS FOR A PARTICULAR PURPOSE.

HEWLETT-PACKARD CO. SHALL NOT BE LIABLE FOR ANY ERRORS OR FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS MANUAL OR THE EXAMPLES CONTAINED HEREIN.

© Copyright 1981, 2004 Hewlett-Packard Development Company, L.P. Reproduction, adaptation, or translation of this manual is prohibited without prior written permission of Hewlett-Packard Company, except as allowed under the copyright laws.

Hewlett-Packard Company 4995 Murphy Canyon Rd, Suite 301 San Diego, CA 92123

Printing History

Edition 4 August 2004

2

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 2 of 209

Introduction

About This Handbook

This hp 12c user's guide is intended to help you get the most out of your investment in your hp 12c Programmable Financial Calculator. Although the excitement of acquiring this powerful financial tool may prompt you to set this handbook aside and immediately begin "pressing buttons," in the long run you'll profit by reading through this handbook and working through the examples it

Following this introduction is a brief section called Making Financial Calculations Easy—which shows you that your hp 12c does just that! The remainder of this handbook is organized basically into three parts:

- Part I (sections 1 through 7) describes how to use the various financial, mathematics, statistics, and other functions (except for programming) provided in the calculator:
 - Section 1 is about Getting Started. It tells you how to use the keyboard, how to do simple arithmetic calculations and chain calculations, and how to use the storage registers ("memories").
 - Section 2 tells you how to use the percentage and calendar functions.
 - Section 3 tells you how to use the simple interest, compound interest, and amortization functions.
 - Section 4 tells you how to do discounted cash flow analysis, bond, and depreciation calculations.
 - Section 5 tells you about miscellaneous operating features such as Continuous Memory, the display, and special function keys.
 - Sections 6 and 7 tell you how to use the statistics, mathematics, and number-alteration functions.
- Part II (sections 8 through 11) describe how to use the powerful programming capabilities of the hp 12c.
- Part III (sections 12 through 16) give you step-by-step solutions to specialized problems in real estate, lending, savings, investment analysis, and bonds. Some of these solutions can be done manually, while others involve running a program. Since the programmed solutions are both self-contained and step-by-step, you can easily employ them even if you don't care to learn how to create your own programs. But if you do start to create your own programs, look over the programs used in the solutions: they contain examples of good programming techniques and practices.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 3 of 209 Dimension: 14.8 cm x 21 cm

Printed Date: 2005/7/29

4 Introduction

- The various appendices describe additional details of calculator operation as well as warranty and service information.
- The Function Key Index and Programming Key Index at the back of the handbook can be used as a handy page reference to the comprehensive information inside the manual

Financial Calculations in the United Kingdom

The calculations for most financial problems in the United Kingdom are identical to the calculations for those problems in the United States — which are described in this handbook. Certain problems, however, require different calculation methods in the United Kingdom than in the United States. Refer to Appendix F for more information.

For More Solutions to Financial Problems

In addition to the specialized solutions found in Sections 12 through 16 of this handbook, many more are available in the optional hp 12c Solutions Handbook. Included are solutions to problems in lending, forecasting, pricing, statistics, savings, investment analysis, personal finance, securities, Canadian mortgages, learning curves in manufacturing, and queuing theory. A Solutions Handbook is available online (www.hp.com/calculators).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 4 of 209

Contents

Introduction	3
About This Handbook	
Financial Calculations in the United Kingdom	
For More Solutions to Financial Problems	
Part I. Problem Solving	15
Section 1: Getting Started	
Power On and Off	
Low-Power Indication	
The Keyboard	
Keying in Numbers	
Digit Separators	
Negative Numbers	
Keying in Large Numbers	
The CLEAR Keys	
Simple Arithmetic Calculations	
Chain Calculations	
Storage Registers	
Storing and Recalling Numbers	
Clearing Storage Registers	
Storage Register Arithmetic	24
Section 2: Percentage and Calendar Functions	26
Percentage Functions	
Percentages	
Net Amount	
Percent Difference	
Percent of Total	28
Calendar Functions	29
Date Format	29
Future or Past Dates	
Number of Days Between Dates	31
Section 3: Basic Financial Functions	32
The Financial Registers	32
Storing Numbers Into the Financial Registers	
Displaying Numbers in the Financial Registers	

File name: hp 12c_user's guide_English_HDPMBF12E44
Printed Date: 2005/7/29 Page: 5 of 209

Contents

Clearing the Financial Registers	33
Simple Interest Calculations	33
Financial Calculations and the Cash Flow Diagram	34
The Cash Flow Sign Convention	36
The Payment Mode	37
Generalized Cash Flow Diagrams	37
Compound Interest Calculations	
Specifying the Number of Compounding Periods and the Period	
Interest Rate	
Calculating the Number of Payments or Compounding Periods	
Calculating the Periodic and Annual Interest Rates	
Calculating the Present Value	
Calculating the Payment Amount	
Calculating the Future Value	
Odd-Period Calculations	
Amortization	54
Section 4: Additional Financial Functions	. 57
Discounted Cash Flow Analysis: NPV and IRR	
Calculating Internal Rate of Return (IRR)	
Reviewing Cash Flow Entries	
Changing Cash Flow Entries	
Bond Calculations	
Bond Price	
Bond Yield	
Depreciation Calculations	
·	
Section 5: Additional Operating Features	. 70
Continuous Memory	70
The Display	71
Status Indicators	71
Number Display Formats	
Scientific Notation Display Format	72
Special Displays	73
The xxy key	74
The LSTX Key	
Arithmetic Calculations With Constants	
Recovering From Errors in Digit Entry	75

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 6 of 209

Section 6: Statistics Functions	7 6
Accumulating Statistics	
Correcting Accumulated Statistics	
Mean	
Standard Deviation	
Linear Estimation	
Weighted Mean	۱ ۵
Section 7: Mathematics and Number-Alteration Fund	ctions 83
One-Number Functions	83
The Power Function	
Part II. Programming	87
Section 8: Programming Basics	88
Why Use Programs?	88
Creating a Program	
Running a Program	
Program Memory	
Identifying Instructions in Program Lines	
Displaying Program Lines	
The GTO 00 Instruction and Program Line 00	
Expanding Program Memory	
Setting the Calculator to a Particular Program Line Executing a Program One Line at a Time	
Interrupting Program Execution	
Pausing During Program Execution	
Stopping Program Execution	
Section 9: Branching and Looping	
Simple Branching	
Looping	
Conditional Branching	107
Section 10: Program Editing	113
Changing the Instruction in a Program Line	113
Adding Instructions at the End of a Program	
Adding Instructions Within a Program	
Adding Instructions by Replacement	
Adding Instructions by Branching	116

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 7 of 209

Contents

Section 11: Multiple Programs	120
Storing Another Program Running Another Program	
Part III. Solutions	123
Section 12: Real Estate and Lending	124
Annual Percentage Rate Calculations With Fees	126 128 130
Section 13: Investment Analysis	136
Partial-Year Depreciation Straight-Line Depreciation Declining-Balance Depreciation Sum-of-the-Years-Digits Depreciation Full- and Partial-Year Depreciation with Crossover Excess Depreciation Modified Internal Rate of Return	136 139 141 144
Section 14: Leasing	151
Advance Payments	151 154 156 156
Section 15: Savings	160
Nominal Rate Converted to Effective Rate	161
Section 16: Bonds	163
30/360 Day Basis Bonds	

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 8 of 209

Appendixes	169
Appendix A: The Automatic Memory Stack	170
Getting Numbers Into the Stack: The ENTER Key	171
Termination of Digit Entry	172
Stack Lift	
Rearranging Numbers in the Stack	
The XXY key	
The RJ Key	
One-Number Functions and the Stack	
Two-Number Functions and the Stack	
Mathematics Functions	
Percentage Functions	
Calendar and Financial Functions	
The LAST X Register and the LSTX Key	
Chain Calculations	
Arithmetic Calculations with Constants	177
Appendix B: More About IRR	
Appendix C: Error Conditions	
Error 0: Mathematics	
Error 1: Storage Register Overflow	
Error 2: Statistics	
Error 3: IRR	
Error 4: Memory	
Error 5: Compound Interest	
Error 6: Storage Registers	
Error 7: IRR	
Error 8: Calendar	184
Error 9: Service	184
Pr Error	184
Appendix D: Formulas Used	185
Percentage	
Interest	
Simple Interest	
Compound Interest	
Amortization	
Discounted Cash Flow Analysis	
Net Present Value	
Internal Rate of Return	
Calendar	
Actual Day Rasis	

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 9 of 209

10 Contents

30/360 Day Basis	18/
Bonds	188
Depreciation	189
Straight-Line Depreciation	189
Sum-of-the-Years-Digits Depreciation	189
Declining-Balance Depreciation	190
Modified Internal Rate of Return	190
Advance Payments	190
Interest Rate Conversions	191
Finite Compounding	191
Continuous Compounding	191
Statistics	191
Mean	191
Weighted Mean	191
Linear Estimation	191
Standard Deviation	192
Factorial	192
The Rent or Buy Decision	192
Appendix E: Battery, Warranty, and Service Information	n 193
Battery	
Low-Power Indication	
Installing a New Battery	193
Verifying Proper Operation (Self-Tests)	
Warranty	
Service	197
Regulatory Information	199
Temperature Specifications	199
Noise Declaration	
Disposal of Waste Equipment by Users in Private Household in the)
European Union	200
	201
Appendix F: United Kinadom Calculations	
Appendix F: United Kingdom Calculations	201
Mortgages	
MortgagesAnnual Percentage Rate (APR) Calculations	202
MortgagesAnnual Percentage Rate (APR) Calculations	202 202
Mortgages	202 202 203
MortgagesAnnual Percentage Rate (APR) Calculations	202 202 203

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 10 of 209

Making Financial Calculations Easy

Before you begin to read through this handbook, let's take a look at how easy financial calculations can be with your hp 12c. While working through the examples below, don't be concerned about learning how to use the calculator; we'll cover that thoroughly beginning with Section 1.

Example 1: Suppose you want to ensure that you can finance your daughter's college education 14 years from today. You expect that the cost will be about \$6,000 a year (\$500 a month) for 4 years. Assume she will withdraw \$500 at the beginning of each month from a savings account. How much would you have to deposit into the account when she enters college if the account pays 6% annual interest compounded monthly?

This is an example of a compound interest calculation. All such problems involve at least three of the following quantities:

- n: the number of compounding periods.
- i: the interest rate per compounding period.
- PV: the present value of a compounded amount.
- PMT: the periodic payment amount.
- FV: the future value of a compounded amount.

In this particular example:

- n is 4 years \times 12 periods per year = 48 periods.
- *i* is 6% per year ÷ 12 periods per year = 0.5% per period.
- PV is the quantity to be calculated the present value when the financial transaction begins.
- PMT is \$500.
- FV is zero, since by the time your daughter graduates she (hopefully!) will not need any more money.

To begin, turn the calculator on by pressing the $\overline{\tt ON}$ key. Then, press the keys shown in the **Keystrokes** column below.*

11

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 11 of 209

^{*} If you are not familiar with the use of an hp calculator keyboard, refer to the description on pages 16 and 17.

12 Making Financial Calculations Easy

Note: A battery symbol (*) shown in the lower-left corner of the display when the calculator is on signifies that the available battery power is nearly exhausted. To install new batteries, refer to Appendix E.

The calendar functions and nearly all of the financial functions take some time to produce an answer. (This is typically just a few seconds, but the <code>i</code>, <code>AMORT</code>, <code>IRR</code>, and <code>YTM</code> functions could require a half-minute or more.) During these calculations, the word **running** flashes in the display to let you know that the calculator is running.

Keystrokes f CLEARREG f 2	Display 0.00	Clears previous data inside the calculator and sets display to show two decimal places.
4 9 12x	48.00	Calculates and stores the number of compounding periods.
6 g 12÷	0.50	Calculates and stores the periodic interest rate.
500 PMT	500.00	Stores periodic payment amount.
g BEG	500.00	Sets payment mode to Begin.
PV	-21,396.61	Amount required to be deposited.*

Example 2: We now need to determine how to accumulate the required deposit by the time your daughter enters college 14 years from now. Let's say that she has a paid-up \$5,000 insurance policy that pays 5.35% annually, compounded semiannually. How much would it be worth by the time she enters college? In this example, we need to calculate *FV*, the future value.

Keystrokes f CLEAR FIN	Display -21,396.61	Clears previous financial data inside the calculator.
14 ENTER 2 X n	28.00	Calculates and stores the number of compounding periods.
5.35 NTER 2 ÷ i	2.68	Calculates and stores the periodic interest rate.
5000 CHS PV	-5,000.00	Stores the present value of the policy.
FV	10,470.85	Value of policy in 14 years.

^{*} Don't be concerned now about the minus sign in the display. That and other details will be explained in Section 3.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 12 of 209

Example 3: The preceding example showed that the insurance policy will provide about half the required amount. An additional amount must be set aside to provide the balance (21,396.61 – 10,470.85 = 10,925.76). Suppose you make monthly payments, beginning at the end of next month, into an account that pays 6% annually, compounded monthly. What payment amount would be required in order to accumulate \$10,925.75 in the 14 years remaining?

Keystrokes	Display	
f CLEAR FIN	10,470.85	Clears previous financial data inside the calculator.
14g12x	168.00	Calculates and stores the number of compounding periods.
6 9 12÷	0.50	Calculates and stores the periodic interest rate.
10925.76 _{FV}	10.925.76	Stores the future value required.
9 END	10.925.76	Sets payment mode to End.
PMT	-41.65	Monthly payment required.

Example 4: Suppose you cannot find a bank that currently offers an account with 6% annual interest compounded monthly, but you can afford to make \$45.00 monthly payments. What is the minimum interest rate that will enable you to accumulate the required amount?

In this problem, we do not need to clear the previous financial data inside the calculator, since most of it is unchanged from the preceding example.

Keystrokes	Display	
45 CHS PMT	-45.00	Stores payment amount
i	0.42	Periodic interest rate.
12×	5.01	Annual interest rate.

This is only a small sampling of the many financial calculations that can now be done easily with your hp 12c. To begin learning about this powerful financial tool, just turn the page.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 13 of 209



Section 1

Getting Started

Power On and Off

To begin using your hp 12c, press the ON key*. Pressing ON again turns the calculator off. If not manually turned off, the calculator will turn off automatically 8 to 17 minutes after it was last used.

Low-Power Indication

A battery symbol (*) shown in the upper-left corner of the display when the calculator is on signifies that the available battery power is nearly exhausted. To replace the batteries, refer to Appendix E.

The Keyboard

Many keys on the hp 12c perform two or even three functions. The primary function of a key is indicated by the characters printed in white on the upper face of the key. The alternate function(s) of a key are indicated by the characters printed in gold above the key and the characters printed in blue on the lower face of the key. These alternate functions are specified by pressing the appropriate prefix key before the function key:



- To specify the alternate function printed in gold above a key, press the gold prefix key (f), then press the function key.
- To specify the primary function printed on the upper face of a key, press the key alone.
- To specify the alternate function printed in blue on the lower face of a key, press the blue prefix key (9), then press the function key.

16

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 16 of 209

^{*} Note that the ON key is lower than the other keys to help prevent its being pressed inadvertently.

Throughout this handbook, references to the *operation* of an alternate function appear as only the function name in a box (for example, "The $\overline{\tt IRR}$ function ..."). References to the *selection* of an alternate function appear preceded by the appropriate prefix key (for example, "Pressing $\overline{\tt f.IRR}$..."). References to the functions shown on the keyboard in gold under the bracket labeled "CLEAR" appear throughout this handbook preceded by the word "CLEAR" (for example, "The CLEARREG function ..." or "Pressing $\overline{\tt f.CLEARREG}$...").

If you press the <code>f</code> or <code>g</code> prefix key mistakenly, you can cancel it by pressing <code>f</code> CLEAR This can also be pressed to cancel the <code>STO</code>, <code>RCL</code>, and <code>GTO</code> keys. (These keys are "prefix" keys in the sense that other keys must be pressed after them in order to execute the corresponding function.) Since the <code>PREFIX</code> key is also used to display the mantissa (all 10 digits) of a displayed number, the mantissa of the number in the display will appear for a moment after the <code>PREFIX</code> key is released.

Pressing the f or g prefix key turns on the corresponding status indicator — f or g — in the display. Each indicator turns off when you press a function key (executing an alternate function of that key), another prefix key, or f CLEAR PREFIX.

Keying in Numbers

To key a number into the calculator, press the digit keys in sequence, just as if you were writing the number on paper. A decimal point must be keyed in (using the decimal point key) if it is part of the number unless it appears to the right of the last digit.

Digit Separators

As a number is keyed in, each group of three digits to the left of the decimal point is automatically separated in the display. When the calculator is first turned on after coming from the factory — or after Continuous Memory is reset — the decimal point in displayed numbers is a dot, and the separator between each group of three digits is a comma. If you wish, you can set the calculator to display a comma for the decimal point and a dot for the three-digit separator. To do so, turn the calculator off, then press and hold down the • key while you press ON. Doing so again sets the calculator to use the original digit separators in the display.

Negative Numbers

To make a displayed number negative — either one that has just been keyed in or one that has resulted from a calculation — simply press $\overline{\text{CHS}}$ (change sign). When the display shows a negative number — that is, the number is preceded by a minus sign — pressing $\overline{\text{CHS}}$ removes the minus sign from the display, making the number positive.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 17 of 209

Keying in Large Numbers

Since the display cannot show more than 10 digits of a number, numbers greater than 9,999,999,999 cannot be entered into the display by keying in all the digits in the number. However, such numbers can be easily entered into the display if the number is expressed in a mathematical shorthand called "scientific notation." To convert a number into scientific notation, move the decimal point until there is only one digit (a nonzero digit) to its left. The resulting number is called the "mantissa" of the original number, and the number of decimal places you moved the decimal point is called the "exponent" of the original number. If you moved the decimal point to the left, the exponent is positive; if you moved the decimal point to the right (this would occur for numbers less than one), the exponent is negative. To key the number into the display, simply key in the mantissa, press <code>EEX</code> (enter exponent), then key in the exponent. If the exponent is negative, press <code>GHS</code> after pressing <code>EEX</code>.

For example, to key in \$1,781,400,000,000, we move the decimal point 12 places to the left, giving a mantissa of 1.7814 and an exponent of 12:

Keystrokes	Display	
1.7814 EEX 12	1.7814 12	1,781,400,000,000 entered in
		scientific notation.

Numbers entered in scientific notation can be used in calculations just like any other number.

The CLEAR Keys

Clearing a register or the display replaces the number in it with zero. Clearing program memory replaces the instructions there with <code>g_GTO</code>00. There are several clearing operations on the hp 12c, as shown in the table below:

Key(s)	Clears:
CLX	Display and X-register.
$fCLEAR\Sigma$	Statistics registers (R_1 through R_6), stack registers, and display.
f CLEAR PRGM	Program memory (only when pressed in Program mode).
f CLEAR FIN	Financial registers.
f CLEAR REG	Data storage registers, financial registers, stack and LAST X registers, and display.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 18 of 209

Simple Arithmetic Calculations

Any simple arithmetic calculation involves two numbers and an operation — addition, subtraction, multiplication, or division. To do such a calculation on your hp 12c, you first tell the calculator the two numbers, *then* tell the calculator the operation to be performed. The answer is calculated when the operation key $(+, -, \times)$, or \div) is pressed.

The two numbers should be keyed into the calculator in the order they would appear if the calculation were written down on paper left-to-right. After keying in the first number, press the <code>EMER</code> key to tell the calculator that you have completed entering the number. Pressing <code>EMER</code> separates the second number to be entered from the first number already entered.

In summary, to perform an arithmetic operation:

- 1. Key in the first number.
- 2. Press ENTER to separate the second number from the first.
- 3. Key in the second number.
- 4. Press +, -, \times , or \div to perform the desired operation.

For example to calculate $13 \div 2$, proceed as follows:

Keystrokes	Display	
13	13.	Keys the first number into the calculator.
ENTER	13.00	Pressing ENTER separates the second number from the first.
2	2.	Keys the second number into the calculator.
÷	6.50	Pressing the operation key calculates the answer.

Notice that after you pressed $\overline{\mathbb{MR}}$, two zeroes appeared following the decimal point. This is nothing magical: the calculator's display is currently set to show two decimal places of every number that has been entered or calculated. Before you pressed $\overline{\mathbb{MR}}$, the calculator had no way of knowing that you had completed entering the number, and so displayed only the digits you had keyed in. Pressing $\overline{\mathbb{MR}}$ tells the calculator that you have completed entering the number: it *terminates digit entry*. You need not press $\overline{\mathbb{MR}}$ after keying in the second number because the $\overline{+}$, $\overline{-}$, $\overline{\times}$ and $\overline{\div}$ keys also terminate digit entry. (In fact, all keys terminate digit entry except for digit entry keys $\overline{-}$ digit keys, $\overline{-}$, $\overline{\mathbb{CHS}}$, and $\overline{\mathbb{EEX}}$ $\overline{-}$ and prefix keys $\overline{-}$ f, $\overline{\mathbb{Q}}$, $\overline{\mathbb{STO}}$, $\overline{\mathbb{RCL}}$, and $\overline{\mathbb{GTO}}$.)

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 19 of 209

Chain Calculations

Whenever the answer has just been calculated and is therefore in the display, you can perform another operation with this number by simply keying in the second number and then pressing the operation key: you need *not* press to separate the second number from the first. This is because when a number is keyed in after a function key (such as $+,-,\times$, \div , etc.) is pressed, the result of that prior calculation is stored inside the calculator — just as when the + key is pressed. The only time you must press the + key to separate two numbers is when you are keying them both in, one immediately following the other.

The hp 12c is designed so that each time you press a function key in RPN mode, the calculator performs the operation then — not later — so that you see the results of all intermediate calculations, as well as the "bottom line."

Example: Suppose you've written three checks without updating your checkbook, and you've just deposited your paycheck for \$1,053.00 into your checking account. If your latest balance was \$58.33 and the checks were written for \$22.95, \$13.70, and \$10.14, what is the new balance?


Solution: When written down on paper, this problem would read 58.33 - 22.95 - 13.70 - 10.14 + 1053

Keystrokes	Display	
58.33	58.33	Keys the first number.
ENTER	58.33	Pressing ENER separates the second number from the first.
22.95	22.95	Keys in the second number.
	35.38	Pressing — subtracts the second number from the first. The calculator displays the result of this calculation, which is the balance after subtracting the first check.
13.70	13.70	Keys in the next number. Since a calculation has just been performed, do not press [MTH]; the next number entered (13.70) is automatically separated from the one previously in the display (35.38).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 20 of 209


Keystrokes	Display	
	21.68	Pressing — subtracts the number just entered from the number previously in the display. The calculator displays the result of this calculation, which is the balance after subtracting the second check.
10.14	11.54	Keys in the next number and subtracts it from the previous balance. The new balance appears in the display. (It's getting rather low!)
1053 🛨	1,064.54	Keys in the next number — the paycheck deposited — and adds it to the previous balance. The new, current balance appears in the display.

The preceding example demonstrates how the hp 12c calculates just as you would using pencil and paper (except a lot faster!):



Let's see this happening in a different type of calculation — one that involves multiplying groups of two numbers and then adding the results. (This is the type of calculation that would be required to total up an invoice consisting of several items with different quantities and different prices.)

For example, consider the calculation of $(3 \times 4) + (5 \times 6)$. If you were doing this on paper, you would first do the multiplication in the first parentheses, then the multiplication in the second parentheses, and finally add the results of the two multiplications:



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 21 of 209

22 Section 1: Getting Started

Your hp 12c calculates the answer in just the same way:

Keystrokes	Display	
3 ENTER 4 X	12.00	Step 1: Multiply the numbers in the first parentheses.
5 ENTER 6 X	30.00	Step 2: Multiply the numbers in the second parentheses.
+	42.00	Step 3: Add the results of the two multiplications.

Notice that before doing step 2, you did not need to store or write down the result of step 1: it was stored inside the calculator automatically. And after you keyed in the 5 and the 6 in step 2, the calculator was holding two numbers (12 and 5) inside for you, in addition to the 6 in the display. (The hp 12c can hold a total of three numbers inside, in addition to the number in the display.) After step 2, the calculator was still holding the 12 inside for you, in addition to the 30 in the display. You can see that the calculator holds the number for you, just as you would have them written on paper, and then calculates with them at the proper time, just as you would yourself.* But with the hp 12c, you don't need to write down the results of an intermediate calculation, and you don't even need to manually store it and recall it later.

By the way, notice that in step 2 you needed to press EMTER again. This is simply because you were again keying in two numbers immediately following each other, without performing a calculation in between.

To check your understanding of how to calculate with your hp 12c, try the following problems yourself. Although these problems are relatively simple, more complicated problems can be solved using the same basic steps. If you have difficulty obtaining the answers shown, review the last few pages.

$$(3+4) \times (5+6) = 77.00$$
$$\frac{(27-14)}{(14+38)} = 0.25$$
$$\frac{5}{3+16+21} = 0.13$$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 22 of 209

^{*} Although you don't need to know just how these numbers are stored and brought back at just the right time, if you're interested you can read all about it in Appendix A. By gaining a more complete understanding of the calculator's operation, you'll use it more efficiently and confidently, yielding a better return on the investment in your hp 12c.

Storage Registers

Numbers (data) in the hp 12c are stored in memories called "storage registers" or simply "registers." (The singular term " memory" is sometimes used in this handbook to refer to the entire collection of storage registers.) Four special registers are used for storing numbers during calculations (these "stack registers" are described in Appendix A), and another (called the "LAST X" register) is used for storing the number last in the display before an operation is performed. In addition to these registers into which numbers are stored automatically, up to 20 "data storage" registers are available for manual storage of numbers. These data storage registers are designated $R_{\scriptscriptstyle 0}$ through $R_{\scriptscriptstyle 0}$ through $R_{\scriptscriptstyle 0}$. Fewer registers are available for data storage if a program has been stored in the calculator (since the program is stored in some of those 20 registers), but a minimum of 7 registers is always available. Still other storage registers — referred to as the "financial registers" — are reserved for numbers used in financial calculations.

Storing and Recalling Numbers

To store the number from the display into a data storage register:

- 1. Press STO (store).
- 2. Key in the register number: 0 through 9 for registers R_0 through R_0 , or 0 through 9 for registers R_0 through 0.

Similarly, to recall a number from a storage register into the display, press RCL (recall), then key in the register number. This copies the number from the storage register into the display; the number remains unaltered in the storage register. Furthermore, when this is done, the number previously in the display is automatically held inside the calculator for a subsequent calculation, just as the number in the display is held when you key in another number.

Example: Before you leave to call on a customer interested in your personal computer, you store the cost of the computer (\$3,250) and also the cost of a printer (\$2,500) in data storage registers. Later, the customer decides to buy six computers and one printer. You recall the cost of the computer, multiply by the quantity ordered, and then recall and add the cost of the printer to get the total invoice.

Keystrokes	Display	
3250STO1	3,250.00	Stores the cost of the computer in R_1 .
2500 STO 2	2,500.00	Stores the cost of the printer in R_2 .
ON		Turns the calculator off.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 23 of 209

24 Section 1: Getting Started

Later that same day ...

Keystrokes	Display	
ON	2,500.00	Turns the calculator back on.
RCL 1	3,250.00	Recalls the cost of the computer to the display.
6 <u>x</u>	19,500.00	Multiplies the quantity ordered to get the cost of the computers.
[RCL]2	2,500.00	Recalls the cost of the printer to the display.
+	22,000.00	Total invoice.

Clearing Storage Registers

To clear a single storage register — that is, to replace the number in it with zero — merely store zero into it. You need not clear a storage register before storing data into it; the storing operation automatically clears the register before the data is stored.

To clear *all* storage registers at once — including the financial registers, the stack registers, and the LAST X register — press f CLEARREG.* This also clears the display.

All storage registers are also cleared when Continuous Memory is reset (as described on page 70).

Storage Register Arithmetic

Suppose you wanted to perform an arithmetic operation with the number in the display and the number in a storage register, then store the result back into the same register without altering the number in the display. The hp 12c enables you to do all this in a single operation:

- 1. Press STO.
- 2. Press \pm , -, \times , or \pm to specify the desired operation.
- 3. Key in the register number.

When storage register arithmetic is performed, the new number in the register is determined according to the following rule:

$$\begin{array}{ccc} \text{number now} & = & \text{number formerly} & \left\{ \begin{array}{c} + \\ - \\ \times \\ \vdots \end{array} \right\} & \text{number in display} \end{array}$$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 24 of 209

^{*} CLEAR REG is not programmable.

Storage register arithmetic is possible with only registers $R_{_{\!0}}$ through $R_{_{\!4}}$

Example: In the example on page 20, we updated the balance in your checkbook. Let's suppose that because data is stored indefinitely in your calculator's Continuous Memory, you keep track of your checking account balance in the calculator. You could use storage register arithmetic to quickly update the balance after depositing or writing checks.

Keystrokes	Display	
58.33STO0	58.33	Stores the current balance in register $\rm R_{\rm o}$.
22.95 <u>STO</u> - 0	22.95	Subtracts the first check from the balance in R_{\circ} . Note that the display continues to show the amount subtracted; the answer is placed only in R_{\circ} .
13.70STO - 0	13.70	Subtracts the second check.
10.14STO - 0	10.14	Subtracts the third check.
1053STO +0	1,053.00	Adds the deposit.
RCL 0	1,064.54	Recalls the number in ${\bf R}_{\rm o}$ to check the new balance.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 25 of 209

Section 2

Percentage and Calendar Functions

Percentage Functions

The hp 12c includes three keys for solving percentage problems: %, $\Delta\%$, and %T. You don't need to convert percentages to their decimal equivalents; this is done automatically when you press any of these keys. Thus, 4% need not be changed to 0.04; you key it in the way you see and say it: 4%.

Percentages

To find the amount corresponding to a percentage of a number:

- 1. Key in the base number.
- 2. Press ENTER.
- 3. Key in the percentage.

For example, to find 14% of \$300:

Keystrokes	Display	
300	300.	Keys in the base number.
ENTER	300.00	Pressing EMER separates the next number entered from the first number, just as when an ordinary arithmetic calculation is performed.
14	14.	Keys in the percentage.
%	42.00	Calculates the amount.

If the base number is already in the display as a result of a previous calculation, you should not press $\overline{\mathbb{MB}}$ before keying in the percentage — just as in a chain arithmetic calculation.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 26 of 209

Net Amount

A net amount — that is, the base amount plus or minus the percentage amount — can be calculated easily with your hp 12c, since the calculator holds the base amount inside after you calculate a percentage amount. To calculate a net amount, simply calculate the percentage amount, then press \pm or -.

Example: You're buying a new car that lists for \$13,250. The dealer offers you a discount of 8%, and the sales tax is 6%. Find the amount the dealer is charging you, then find the total cost to you, including tax.

Keystrokes	Display	
13250EVER	13,250.00	Keys in the base amount and separates it from the percentage.
8 [%]	1,060.00	Amount of discount.
_	12,190.00	Base amount less discount.
6 %	731.40	Amount of tax (on \$12,190).
+	12,921.40	Total cost: base amount less discount plus tax.

Percent Difference

To find the percent difference between two numbers:

- 1. Key in the base number.
- 2. Press ENTER to separate the other number from the base number.
- 3. Key in the other number.
- 4. Press Δ%.

If the other number is greater than the base number, the percent difference will be positive. If the other number is less than the base number, the percent difference will be negative. Therefore, a positive answer indicates an increase, while a negative answer indicates a decrease.

If you are calculating a percent difference over time, the base number is typically the amount occurring first.

Example: Yesterday your stock fell from $58^{1}/_{2}$ to $53^{1}/_{4}$ per share. What is the percent change?

Keystrokes	Display	
58.5 ENTER	58.50	Keys in the base number and separates it from the other number.
53.25	53.25	Keys in the other number.
Δ%	-8.97	Nearly a 9% decrease.
Δ%	-8.97	Nearly a 9% decrease.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 27 of 209

28 Section 2: Percentage and Calendar Functions

The $\Delta\%$ key can be used for calculations of the percent difference between a wholesale cost and a retail cost. If the base number entered is the wholesale cost, the percent difference is called the *markup*; if the base number entered is the retail cost, the percent difference is called the *margin*. Examples of markup and margin calculations are included in the *hp 12c Solutions Handbook*.

Percent of Total

To calculate what percentage one number is of another:

- 1. Calculate the total amount by adding the individual amounts, just as in a chain arithmetic calculation.
- 2. Key in the number whose percentage equivalent you wish to find.
- 3. Press %T.

Example: Last month, your company posted sales of \$3.92 million in the U.S., \$2.36 million in Europe, and \$1.67 million in the rest of the world. What percentage of the total sales occurred in Europe?

Keystrokes	Display	
3.92 ENTER	3.92	Keys in the first number and separates it from the second.
2.36 +	6.28	Adds the second number.
1.67 +	7.95	Adds the third number to get the total.
2.36	2.36	Keys in 2.36 to find what percentage it is of the number in the display.
%T	29.69	Europe had nearly 30% of the total sales.

The hp 12c holds the total amount inside after a percent of total is calculated. Therefore, to calculate what percentage *another* amount is of the total:

- 1. Clear the display by pressing CLx.
- 2. Key in that amount.
- 3. Press %T again.

For example, to calculate what percent of the total sales in the preceding example occurred in the U.S. and what percent occurred in the rest of the world:

Keystrokes	Display	
CLx 3.92 %T	49.31	The U.S. had about 49% of the total sales.
CLx 1.67 %T	21.01	The rest of the world had about 21% of the total sales.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 28 of 209

To find what percentage a number is of a total, when you already know the total number:

- 1. Key in the total number.
- 2. Press ENTER to separate the other number from the total number.
- 3. Key in the number whose percentage equivalent you wish to find.
- 4. Press %T.

For example, if you already knew in the preceding example that the total sales were \$7.95 million and you wanted to find what percentage of that total occurred in Europe:

Keystrokes	Display	
7.95 ENTER	7.95	Keys in the total amount and separates it from the next number.
2.36	2.36	Keys in 2.36 to find what percentage it is of the number in the display.
<u>%T</u>	29.69	Europe had nearly 30% of the total sales.

Calendar Functions

The calendar functions provided by the hp 12c-DATE and ADYS-can handle dates from October 15, 1582 through November 25, 4046.

Date Format

For each of the calendar functions — and also for bond calculations ($\overline{\text{YTM}}$) — the calculator uses one of two date formats. The date format is used to interpret dates when they are keyed into the calculator as well as for displaying dates.

Month-Day-Year. To set the date format to month-day-year, press <code>9 M.DY</code>. To key in a date with this format in effect:

- 1. Key in the one or two digits of the month.
- 2. Press the decimal point key (•).
- 3. Key in the two digits of the day.
- 4. Key in the four digits of the year.

Dates are displayed in the same format.

For example, to key in April 7, 2004:

Keystrokes	Display
4.072004	4.072004

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 29 of 209

30 Section 2: Percentage and Calendar Functions

Page: 30 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Keystrokes	Display	
14.052004 ENTER	14.05	Keys in date and separates it from number of days to be entered.
120 9 DATE	11,09,2004 6	The expiration date is 11 September 2004, a Saturday.

When DATE is executed as an instruction in a running program, the calculator pauses for about 1 second to display the result, then resumes program execution.

Number of Days Between Dates

To calculate the number of days between two given dates:

- 1. Key in the earlier date and press ENTER.
- 2. Key in the later date and press 9 ADYS.

The answer shown in the display is the actual number of days between the two dates, including leap days (the extra days occurring in leap years), if any. In addition, the hp 12c also calculates the number of days between the two dates on the basis of a 30-day month. This answer is held inside the calculator; to display it, press $x \in Y$. Pressing $x \in Y$ again will return the original answer to the display.

Example: Simple interest calculations can be done using either the actual number of days or the number of days counted on the basis of a 30-day month. What would be the number of days counted each way, to be used in calculating the simple interest accruing from June 3, 2004 to October 14, 2005? Assume that you normally express dates in the month-day-year format.

Keystrokes	Display	
g M.DY	11.09	Sets date format to month-day-year. (Display shown assumes date remains from preceding example.)
6.032004 ENTER	6.03	Keys in earlier date and separates it from the later date.
10.142005 g ADYS	498.00	Keys in later date. Display shows actual number of days.
[X ≶ Å]	491.00	Number of days counted on the basis of a 30-day month.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 31 of 209

Section 3

Basic Financial Functions

The Financial Registers

In addition to the data storage registers discussed on page 23, the hp 12c has five special registers in which numbers are stored for financial calculations. These registers are designated n, i, PV, PMT, and FV. The first five keys on the top row of the calculator are used to store a number from the display into the corresponding register, to calculate the corresponding financial value and store the result into the corresponding register, or to display the number stored in the corresponding register.*

Storing Numbers Into the Financial Registers

To store a number into a financial register, key the number into the display, then press the corresponding key (\boxed{n} , \boxed{i} , \boxed{PV} , \boxed{PMT} , or \boxed{FV}).

Displaying Numbers in the Financial Registers

To display a number stored in a financial register, press $\overline{\text{RCL}}$ followed by the corresponding key.†

32

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 32 of 209

^{*} Which operation is performed when one of these keys is pressed depends upon the last preceding operation performed: If a number was just stored into a financial register (using n, i, PV, PMT, FV, 12X, or 12±), pressing one of these five keys calculates the corresponding value and stores it into the corresponding register; otherwise pressing one of these five keys merely stores the number from the display into the corresponding register.

[†] It's good practice to press the corresponding key *twice* after RCL, since often you may want to calculate a financial value right after displaying another financial value. As indicated in the preceding footnote, if you wanted to display FV and then calculate PV, for example, you should press RCLFV|FV|FV|PV|. If you didn't press FV the second time, pressing PV would store FV in the PV register rather than calculating PV, and to calculate PV you would have to press PV again.

Clearing the Financial Registers

Every financial function uses numbers stored in several of the financial registers. Before beginning a new financial calculation, it is good practice to clear all of the financial registers by pressing <code>fCLEARFIN</code>. Frequently, however, you may want to repeat a calculation after changing a number in only one of the financial registers. To do so, do not press <code>fCLEARFIN</code>; instead, simply store the new number in the register. The numbers in the other financial registers remain unchanged.

The financial registers are also cleared when you press fCLEARREG and when Continuous Memory is reset (as described on page 70).

Simple Interest Calculations

The hp 12c simultaneously calculates simple interest on both a 360-day basis and a 365-day basis. You can display either one, as described below. Furthermore, with the accrued interest in the display, you can calculate the total amount (principal plus accrued interest) by pressing +.

- 1. Key in or calculate the number of days, then press n.
- 2. Key in the annual interest rate, then press i.
- 3. Key in the principal amount, then press CHS PV.*
- Press fint to calculate and display the interest accrued on a 360-day basis.
- 5. If you want to display the interest accrued on a 365-day basis, press RIJXEY.
- 6. Press \pm to calculate the total of the principal and the accrued interest now in the display.

The quantities *n*, *i*, and *PV* can be entered in any order.

Example 1: Your good friend needs a loan to start his latest enterprise and has requested that you lend him \$450 for 60 days. You lend him the money at 7% simple interest, to be calculated on a 360-day basis. What is the amount of accrued interest he will owe you in 60 days, and what is the total amount owed?

Keystrokes	Display	
60n	60.00	Stores the number of days.

^{*} Pressing the PV key stores the principal amount in the PV register, which then contains the present value of the amount on which interest will accrue. The CHS key is pressed first to change the sign of the principal amount before storing it in the PV register. This is required by the cash flow sign convention, which is applicable primarily to compound interest calculations.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 33 of 209

Keystrokes	Display	
7 i	7.00	Stores the annual interest rate.
450 CHS PV	-450.00	Stores the principal.
f INT	5.25	Accrued interest, 360-day basis.
+	455.25	Total amount: principal plus accrued interest.

Example 2: Your friend agrees to the 7% interest on the loan from the preceding example, but asks that you compute it on a 365-day basis rather than a 360-day basis. What is the amount of accrued interest he will owe you in 60 days, and what is the total amount owed?

Keystrokes	Display	
60 n 7 i 450 CHS PV	60.00 7.00 -450.00	If you have not altered the numbers in the n, i, and PV registers since the preceding example, you may skip these keystrokes.
f INT R↓ X≥ y	5.18	Accrued interest, 365-day basis.
+	455.18	Total amount: principal plus accrued interest.

Financial Calculations and the Cash Flow Diagram

The concepts and examples presented in this section are representative of a wide range of financial calculations. If your specific problem does not appear to be illustrated in the pages that follow, don't assume that the calculator is not capable of solving it. Every financial calculation involves certain basic elements; but the terminology used to refer to these elements typically differs among the various segments of the business and financial communities. All you need to do is identify the basic elements in your problem, and then structure the problem so that it will be readily apparent what quantities you need to tell the calculator and what quantity you want to solve for.


An invaluable aid for using your calculator in a financial calculation is the *cash flow diagram*. This is simply a pictorial representation of the timing and direction of financial transactions, labeled in terms that correspond to keys on the calculator.

The diagram begins with a horizontal line, called a *time line*. It represents the duration of a financial problem, and is divided into compounding periods. For example, a financial problem that transpires over 6 months with monthly compounding would be diagrammed like this:


File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 34 of 209



The exchange of money in a problem is depicted by vertical arrows. Money you receive is represented by an arrow pointing up from the point in the time line when the transaction occurs; money you pay out is represented by an arrow pointing down.



Suppose you deposited (paid out) \$1,000 into an account that pays 6% annual interest and is compounded monthly, and you subsequently deposited an additional \$50 at the end of each month for the next 2 years. The cash flow diagram describing the problem would look like this:



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 35 of 209

36 Section 3: Basic Financial Functions

The form in which n is entered determines whether or not the calculator performs financial calculations in Odd-Period mode (as described on pages 50 through 53). If n is a *noninteger* (that is, there is at least one nonzero digit to the right of the decimal point), calculations of i, PV, PMT, and FV are performed in Odd-Period mode.

- *i* is the interest rate *per compounding period*. The interest rate shown in the cash flow diagram and entered into the calculator is determined by dividing the annual interest rate by the number of compounding periods. In the problem illustrated above, *i* = 6% ÷ 12.
- PV the present value is the initial cash flow or the present value of a series of future cash flows. In the problem illustrated above, PV is the \$1,000 initial deposit.
- PMT is the period payment. In the problem illustrated above PMT is the \$50 deposited each month. When all payments are equal, they are referred to as annuities. (Problems involving equal payments are described in this section under Compound Interest Calculations; problems involving unequal payments can be handled as described in under Discounted Cash Flow Analysis: NPV and IRR. Procedures for calculating the balance in a savings account after a series of irregular and/or unequal deposits are included in the hp 12c Solutions Handbook.)
- FV the future value is the final cash flow or the compounded value of a series of prior cash flows. In the particular problem illustrated above, FV is unknown (but can be calculated).

Solving the problem is now basically a matter of keying in the quantities identified in the cash flow diagram using the corresponding keys, and then calculating the unknown quantity by pressing the corresponding key. In the particular problem illustrated in the cash flow diagram above, FV is the unknown quantity; but in other problems, as we shall see later, n, i, PV, or PMT could be the unknown quantity. Likewise, in the particular problem illustrated above there are four known quantities that must be entered into the calculator before solving for the unknown quantity; but in other problems only three quantities may be known — which must always include n or i.

The Cash Flow Sign Convention

When entering the PV, PMT, and FV cash flows, the quantities must be keyed into the calculator with the proper sign, + (plus) or - (minus), in accordance with ...

The Cash Flow Sign Convention: Money received (arrow pointing up) is entered or displayed as a positive value (+). Money paid out (arrow pointing down) is entered or displayed as a negative value (-).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 36 of 209

The Payment Mode

One more bit of information must be specified before you can solve a problem involving periodic payments. Such payments can be made either at the beginning of a compounding period (payments in advance, or annuities due) or at the end of the period (payments in arrears, or ordinary annuities). Calculations involving payments in advance yield different results than calculations involving payments in arrears. Illustrated below are portions of cash flow diagrams showing payments in advance (Begin) and payments in arrears (End). In the problem illustrated in the cash flow diagram above, payments are made in arrears.



Regardless of whether payments are made in advance or in arrears, the number of payments must be the same as the number of compounding periods.

To specify the payment mode:

- Press @ BEG if payments are made at the beginning of the compounding periods.
- Press g END if payments are made at the end of the compounding periods.

The **BEGIN** status indicator is lit when the payment mode is set to Begin. If **BEGIN** is not lit, the payment mode is set to End.


The payment mode remains set to what you last specified until you change it; it is not reset each time the calculator is turned on. However, if Continuous Memory is reset, the payment mode will be set to End.


Generalized Cash Flow Diagrams

Examples of various kinds of financial calculations, together with the applicable cash flow diagrams, appear under Compound Interest Calculations later in this section. If your particular problem does not match any of those shown, you can solve it nevertheless by first drawing a cash flow diagram, then keying the quantities identified in the diagram into the corresponding registers. Remember always to observe the sign convention when keying in PV, PMT, and FV.


The terminology used for describing financial problems varies among the different segments of the business and financial communities. Nevertheless, most problems involving compound interest can be solved by drawing a cash flow diagram in one of the following basic forms. Listed below each form are some of the problems to which that diagram applies.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 37 of 209







Mortgage Direct Reduction (Installment) Loan Amortization Ordinary Annuity



Mortgage With Balloon Amortization Ordinary Annuity





 $File\ name:\ hp\ 12c_user's\ guide_English_HDPMBF12E44$

Printered Date: 2005/7/29

Page: 38 of 209

Dimension: 14.8 cm x 21 cm

Compound Interest Calculations

Specifying the Number of Compounding Periods and the Periodic Interest Rate

Interest rates are usually quoted at the *annual rate* (also called the *nominal rate*): that is, the interest rate per year. However, in compound interest problems, the interest rate entered into i must always be expressed in terms of the basic compounding period, which may be years, months, days, or any other time unit. For example, if a problem involves 6% annual interest compounded quarterly for 5 years, n — the number of quarters — would be $5 \times 4 = 20$ and i — the interest rate per quarter — would be $6\% \div 4 = 1.5\%$. If the interest were instead compounded monthly, n would be $5 \times 12 = 60$ and i would be $6\% \div 12 = 0.5\%$.

If you use the calculator to multiply the number of years by the number of compounding periods per year, pressing $\boxed{\mathbf{n}}$ then stores the result into \mathbf{n} . The same is true for \mathbf{i} . Values of n and i are calculated and stored like this in Example 2 on page 47.

If interest is compounded monthly, you can use a shortcut provided on the calculator to calculate and store n and i:

- To calculate and store n, key the number of years into the display, then press
 9 12x
- To calculate and store i, key the annual rate into the display, then press
 g | 12÷ |.

Note that these keys not only multiply or divide the displayed number by 12; they also automatically store the result in the corresponding register, so you need not press the \boxed{n} or \boxed{i} key next. The $\boxed{12x}$ and $\boxed{12\div}$ keys are used in Example 1 on page 46.

Calculating the Number of Payments or Compounding Periods

- 1. Press f CLEAR FIN to clear the financial registers.
- 2. Enter the periodic interest rate, using i or 12÷.
- 3. Enter at least two of the following values:
 - Present value, using PV.
 - Payment amount, using PMT.
 - Future value, using FV.

Note: Remember to observe the cash flow sign convention.


- 4. If a PMT was entered, press 9 BEG or 9 END to set the payment mode.
- 5. Press n to calculate the number of payments or periods.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 39 of 209

If the answer calculated is not an integer (that is, there would be nonzero digits to the right of the decimal point), the calculator rounds the answer up to the next higher integer before storing it in the n register and displaying it.* For example, if n were calculated as 318.15, **319.00** would be the displayed answer.

n is rounded up by the calculator to show the *total* number of payments needed: n-1 equal, full payments, and one final, smaller payment. The calculator does not automatically adjust the values in the other financial registers to reflect n equal payments; rather, it allows you to choose which, if any, of the values to adjust.† Therefore, if you want to know the value of the final payment (with which you can calculate a balloon payment) or desire to know the payment value for n equal payments, you will need to press one of the other financial keys, as shown in the following two examples.

Example 1: You're planning to build a log cabin on your vacation property. Your rich uncle offers you a \$35,000 loan at 10.5% interest. If you make \$325 payments at the end of each month, how many payments will be required to pay off the loan, and how many years will this take?



Display	
0.88	Calculates and stores <i>i</i> . Stores <i>PV</i> .
-325.00	Stores <i>PMT</i> (with minus sign for cash paid out).
-325.00	Sets the payment mode to End.
328.00	Number of payments required.
	0.88 35,000.00 -325.00

^{*} The calculator will round *n* down to the next lower integer if the fractional portion of *n* is less than 0.005.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 40 of 209

[†] After calculating n, pressing i, [PV], [PMT], or [FV] will recalculate the value in the corresponding financial register.

Keystrokes	Display	
12 ÷	27.33	Twenty-seven years and four months.

Because the calculator rounds the calculated value of n up to the next higher integer, in the preceding example it is likely that — while 328 payments will be required to pay off the loan — only 327 full payments of \$325 will be required, the next and final payment being less than \$325. You can calculate the final, fractional, 328th payment as follows:

Keystrokes	Display	
328 n	328.00	Stores total number of payments.*
FV	181.89	Calculates FV — which equals the overpayment if 328 full payments were made.
RCL PMT	-325.00	Recalls payment amount.
+	-143.11	Final, fractional payment.

Alternatively, you could make the fractional payment together with the 327th payment. (Doing so will result in a somewhat smaller total of all payments, since you will not have to pay interest during the 328th payment period.) You can calculate this final, larger, 327th payment (essentially a balloon payment) as follows:


Keystrokes	Display	
327 n	327.00	Stores number of full payments.
FV	-141.87	Calculates FV — which is the balance remaining after 327 full payments.
RCL PMT	-325.00	Recalls payment amount.
+	-466.87	Final, balloon payment.

Instead of having a fractional (or balloon) payment at the end of the loan, you might wish to make 327 or 328 *equal* payments. Refer to "Calculating the Payment Amount" on page 46 for a complete description of this procedure.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 41 of 209

^{*} You could skip this step, since 328 is already stored in the *n* register. If you do so, however, you will need to press FV twice in the next step (for the reason discussed in the first footnote on page 32; you would not have to press FV twice if you had not pressed 12 ÷ after 1 in the example above.) We choose to show this and the following example in a parallel format so that the procedure is easy to remember: the number you key is the number of the final payment — either the fractional payment or the balloon payment — whose amount is to be calculated.

Example 2: You're opening a savings account today (the middle of the month) with a \$775 deposit. The account pays $6^1/_4\%$ interest compounded semimonthly. If you make semimonthly deposits of \$50 beginning next month, how long will it take for your account to reach \$4000?



Keystrokes	Display	
f CLEAR FIN 6.25 ENTER 24 ÷ i	0.26	Calculates and stores i.
775 CHS PV	-775.00	Stores PV (with minus sign for cash paid out).
50 CHS PMT	-50.00	Stores <i>PMT</i> (with minus sign for cash paid out).
4000 FV	4,000.00	Stores FV.
g END	4,000.00	Sets the payment mode to End.
n	58.00	Number of semimonthly deposits.
2 ÷	29.00	Number of months.

As in Example 1, it is likely that only 57 *full* deposits will be required, the next and final deposit being less than \$50. You can calculate this final, fractional, 58th deposit as in Example 1, except that for this example you must subtract the original *FV*. (In Example 1, the original *FV* was zero.) The procedure is as follows:

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 42 of 209

Keystrokes	Display	
FV FV	4,027.27	Calculates FV – which equals the balance in the account if 58 full deposits were made.*
RCL PMT	-50.00	Recalls amount of deposits.
+	3,977.27	Calculates the balance in the account if 57 full deposits were made and interest accrued during the 58 th month.†
4000 🗖	-22.73	Calculates final, fractional, 58 th deposit required to reach \$4,000.

Calculating the Periodic and Annual Interest Rates

- 1. Press f CLEAR FIN to clear the financial registers.
- 2. Enter the number of payments or periods, using \boxed{n} or $\boxed{12X}$.
- 3. Enter at least two of the following values:
 - Present value, using PV.
 - Payment amount, using PMT.
 - Future value, using FV.

Note: Remember to observe the cash flow sign convention.


- 4. If a PMT was entered, press <code>gBEG</code> or <code>gEND</code> to set the payment mode.
- 5. Press i to calculate the periodic interest rate.
- 6. To calculate the annual interest rate, key in the number of periods per year, then press X.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 43 of 209

^{*} In this example, FV must be pressed twice, since the preceding key pressed was \div . If we had stored the number of deposits in n (as we did following Example 1), we would have to press FV only once here, since the preceding key pressed would have been \boxed{n} (as it was following Example 1). Remember that it is not necessary to store the number of payments in n before calculating the amount of the final, fractional payment. (Refer to the preceding footnote.)

[†] You might think that we could calculate the balance in the account after 57 full deposits were made simply by storing that number in n and then calculating FV, as we did using the second method following Example 1. However, this balance would not include the interest accrued during the 58th month.

Example: What annual interest rate must be obtained to accumulate \$10,000 in 8 years on an investment of \$6,000 with quarterly compounding?



Keystrokes	Display	
f CLEAR FIN 8 ENTER 4 X n	32.00	Calculates and stores <i>n</i> .
6000 CHS PV	-6,000.00	Stores <i>PV</i> (with minus sign for cash paid out).
10000 FV	10,000.00	Stores FV.
i	1.61	Periodic (quarterly) interest rate.
4X	6.44	Annual interest rate.

Calculating the Present Value


- 1. Press f CLEAR FIN to clear the financial registers.
- 2. Enter the number of payments or periods, using \boxed{n} or $\boxed{12X}$.
- 3. Enter the periodic interest rate, using i or 12÷.
- 4. Enter either or both of the following:
 - Payment amount, using PMT.
 - Future value, using FV.

Note: Remember to observe the cash flow sign convention.

- 5. If a PMT was entered, press <code>9BEG</code> or <code>9END</code> to set the payment mode.
- 6. Press PV to calculate the present value.


File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 44 of 209

Example 1: You're financing a new car purchase with a loan from an institution that requires 15% interest compounded monthly over the 4-year term of the loan. If you can make payments of \$150 at the end of each month and your down payment will be \$1,500, what is the maximum price you can pay for the car? (Assume the purchase date is one month prior to the date of the first payment.)



Keystrokes	Display	
f CLEAR FIN 4 9 12x	48.00	Calculates and stores <i>n</i> .
15g12÷	1.25	Calculates and stores i.
150CHS PMT	-150.00	Stores <i>PMT</i> (with minus sign for cash paid out).
g END	-150.00	Sets payment mode to End.
PV	5,389.72	Maximum amount of loan.
1500 +	6,889.72	Maximum purchase price.

Example 2: A development company would like to purchase a group of condominiums with an annual net cash flow of \$17,500. The expected holding period is 5 years, and the estimated selling price at that time is \$540,000. Calculate the maximum amount the company can pay for the condominiums in order to realize at least a 12% annual yield.



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 45 of 209

Keystrokes	Display	
f CLEAR FIN		
5 n	5.00	Stores n.
12 i	12.00	Stores i.
17500PMT	17,500.00	Stores <i>PMT</i> . Unlike in the previous problem, here <i>PMT</i> is positive since it represents cash <i>received</i> .
540000 FV	540,000.00	Stores FV.
g END	540,000.00	Sets payment mode to End.
PV	-369,494.09	The maximum purchase price to provide a 12% annual yield. PV is displayed with a minus sign since it represents cash paid out.


Calculating the Payment Amount

- 1. Press f CLEAR FIN to clear the financial registers.
- 2. Enter the number of payments or periods, using \boxed{n} or $\boxed{12X}$.
- 3. Enter the periodic interest rate, using i or 12÷.
- 4. Enter either or both of the following:
 - Present value, using PV.
 - Future value, using FV.

Note: Remember to observe the cash flow sign convention.

- 5. Press 9 BEG or 9 END to set the payment mode.
- 6. Press PMT to calculate the payment amount.


Example 1: Calculate the payment amount on a 29-year, \$43,400 mortgage at $14^1/_4\%$ annual interest.



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 46 of 209

Keystrokes	Display	
f CLEAR FIN 29 g 12x	348.00	Calculates and stores <i>n</i> .
14.25 g 12÷	1.19	Calculates and stores i.
43400 PV	43,400.00	Stores PV.
g END	43,400.00	Sets payment mode to End.
PMT	-523.99	Monthly payment (with minus sign for cash paid out).

Example 2: Looking forward to retirement, you wish to accumulate \$60,000 after 15 years by making deposits in an account that pays $9^3/_4\%$ interest compounded semiannually. You open the account with a deposit of \$3,200 and intend to make semiannual deposits, beginning six months later, from your profit-sharing bonus paychecks. Calculate how much these deposits should be.



Keystroke	s I	Display	
f CLEAR F 15 ENTER 2 X 9.75 ENTER 2	n 3	30.00 4.88	Calculates and stores <i>n</i> . Calculates and stores <i>i</i> .
3200 CHS F	PV -	-3200.00	Stores <i>PV</i> (with minus sign for cash paid out).
60000 FV	•	60,000.00	Stores FV.
g END	•	60,000.00	Sets payment mode to End.
PMT	-	-717.44	Semiannual payment (with minus sign for cash paid out).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 47 of 209


Calculating the Future Value

- 1. Press f CLEAR FIN to clear the financial registers.
- 2. Enter the number of payments or periods, using \boxed{n} or $\boxed{12x}$.
- 3. Enter the periodic interest rate, using i or 12÷.
- 4. Enter either or both of the following:
 - Present value, using PV.
 - Payment amount, using PMT.

Note: Remember to observe the cash flow sign convention.

- 5. If a PMT was entered, press <code>9BEG</code> or <code>9END</code> to set the payment mode.
- 6. Press FV to calculate the future value.


Example 1: In Example 1 on page 46, we calculated that the payment amount on a 29-year, \$43,400 mortgage at $14^1/_4$ % annual interest is \$523.99. If the seller requests a balloon payment at the end of 5 years, what would be the amount of the balloon?



Keystrokes	Display	
f CLEARFIN 5 9 12x 14.25 9 12÷ 43400 PV	60.00 1.19 43,400.00	Calculates and stores <i>n</i> . Calculates and stores <i>i</i> . Stores <i>PV</i> .
523.99 CHS PMT	-523.99	Stores <i>PMT</i> (with minus sign for cash paid out).
g END	-523.99	Sets payment mode to End.
FV	-42,652.37	Amount of balloon payment.


File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 48 of 209

Example 2: If you deposit \$50 a month (at the beginning of each month) into a new account that pays $6^1/_4\%$ annual interest compounded monthly, how much will you have in the account after 2 years?



Keystrokes	Display	
f CLEAR FIN 2 9 12x	24.00	Calculates and stores n.
6.25 g 12÷	0.52	Calculates and stores i.
50[CHS][PMT]	-50.00	Stores <i>PMT</i> (with minus sign for cash paid out).
g BEG	-50.00	Sets payment mode to Begin.
FV	1,281.34	Balance after 2 years.

Example 3: Property values in an unattractive area are depreciating at the rate of 2% per year. Assuming this trend continues, calculate the value in 6 years of property presently appraised at \$32,000.



Keystrokes	Display		
f CLEAR FIN			
6 n	6.00	Stores n.	

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 49 of 209

Page: 50 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm You can calculate *i*, *PV*, *PMT*, and *FV* for transactions involving an odd period simply by entering a *noninteger n*. (A noninteger is a number with at least one nonzero digit to the right of the decimal point.) This places the calculator in Odd-Period mode.* The integer part of *n* (the part to the left of the decimal point) specifies the number of full payment periods, and the fractional part (the part to the right of the decimal) specifies the length of the odd period as a fraction of a full period. The odd period, therefore, cannot be greater than one full period.

The fractional part of n can be determined using either the actual number of odd days or the number of odd days counted on the basis of a 30-day month.† The $\overline{\text{ADYS}}$ function can be used to calculate the number of odd days either way. The fractional part of n is a fraction of a payment period, so the number of odd days must be divided by the number of days in a period. If interest is compounded monthly, for this number you can use either 30, 365/12, or (if the odd period falls entirely within a single month) the actual number of days in that month. Usually, a monthly period is taken to be 30 days long.

At your option, the calculations of i, PV, PMT, and FV can be performed with either simple interest or compound interest accruing during the odd period. If the $\bf C$ status indicator in the display is not lit, simple interest is used. To specify compound interest, turn the $\bf C$ indicator on by pressing \overline{STO} \overline{EEX} . \ddagger Pressing \overline{STO} \overline{EEX} again turns the $\bf C$ indicator off, and calculations will then be performed using simple interest for the odd period.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 51 of 209

^{*} Calculations of *i*, *PMT*, and *FV* are performed using the present value at the end of the odd period. This is equal to the number in the PV register *plus* the interest accrued during the odd period. When calculating *PV* in Odd-Period mode, the calculator returns a value equal to the present value at the *beginning* of the odd period and stores it in the *PV* register.

After calculating *i*, *PV*, *PMT*, or *FV* in Odd-Period mode, you should not try to calculate *n*. If you do, the calculator will switch out of Odd-Period mode and compute *n* without taking the odd period into account. The values in the other financial registers will correspond to the new *n*, but the original assumptions for the problem will be changed.

[†] The two methods of counting odd days will yield slightly different answers. If you are calculating *i* to determine the annual percentage rate (APR) for an odd-period transaction, the lower APR will result if the calculation uses the greater number of odd days determined using the two methods.

[‡] STO EEX is not programmable.

Example 1: A 36-month loan for \$4,500 accrues interest at a 15% annual percentage rate (APR), with the payments made at the end of each month. If interest begins accruing on this loan on February 15, 2004 (so that the first period begins on March 1, 2004), calculate the monthly payment, with the odd days counted on the basis of a 30-day month and compound interest used for the odd period.

Keystrokes	Display	
f CLEAR FIN		Clears financial registers.
g M.DY		Sets date format to month-day-year.
g END		Sets payment mode to End.
STO EEX		Turns on the C indicator in the display, so that compound interest will be used for the odd period.
2.152004 NTER	2.15	Keys in the date interest begins accruing and separates it from the next date entered.
3.012004	3.012004	Keys in the date of the beginning of the first period.
g \DYS	15.00	Actual number of odd days.
[X \in y]	16.00	Number of odd days counted on the basis of a 30-day month.
30÷	0.53	Divides by the length of a monthly period to get the fractional part of <i>n</i> .
36+n	36.53	Adds the fractional part of n to the number of complete payment periods, then stores the result in n .
15g12÷	1.25	Calculates and stores i.
4500 PV	4,500.00	Stores PV.
PMT	-157.03	Monthly payment.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 52 of 209

Example 2: A 42-month car loan for \$3,950 began accruing interest on July 19, 2004, so that the first period began on August 1, 2004. Payments of \$120 are made at the end of each month. Calculate the annual percentage rate (APR), using the actual number of odd days and simple interest for the odd period.

Keystrokes	Display	
f CLEAR FIN		Clears financial registers.
STO EEX		Turns off the C indicator in the display, so that simple interest will be used for the odd period.
7.192004[NTER	7.19	Keys in the date interest begins accruing and separates it from the next date entered.
8.012004	8.012004	Keys in the date of the beginning of the first period.
g ADYS	13.00	Actual number of odd days.
30÷	0.43	Divides by the length of a monthly period to get the fractional part of <i>n</i> .
42+n	42.43	Adds the fractional part of <i>n</i> to the number of complete payment periods, then stores the result in <i>n</i> .
3950PV	3,950.00	Stores PV.
120 CHS PMT	-120.00	Stores <i>PMT</i> (with minus sign for cash paid out).
i	1.16	Periodic (monthly) interest rate.
12×	13.95	Annual percentage rate (APR).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 53 of 209

Amortization

The hp 12c enables you to calculate the amounts applied toward principal and toward interest from a single loan payment or from several payments, and also tells you the remaining balance of the loan after the payments are made.*

To obtain an amortization schedule:

- 1. Press f CLEAR FIN to clear the financial registers.
- 2. Enter the periodic interest rate, using i or 12÷.
- 3. Enter the amount of the loan (the principal), using PV.
- 4. Key in the periodic payment, then press CHS PMT (the sign of PMT must be negative, in accordance with the cash flow sign convention).
- Press 9 BEG or (for most direct reduction loans) 9 END to set the payment mode.
- 6. Key in the number of payments to be amortized.
- Press f MORT to display the amount from those payments applied toward interest.
- Press Xey to display the amount from those payments applied toward the principal.
- 9. To display the number of payments just amortized, press RiRi.
- 10. To display the remaining balance of the loan, press RCL PV.
- 11.To display the total number of payments amortized, press RCL n.

Example: For a house you're about to buy, you can obtain a 25-year mortgage for \$50,000 at $13^{1}/_{4}\%$ annual interest. This requires payments of \$573.35 (at the end of each month). Find the amounts that would be applied to interest and to the principal from the first year's payments.

Keystrokes	Display		
f CLEAR FIN			
13.25 g 12÷	1.10	Enters i.	
50000 PV	50,000.00	Enters PV	

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 54 of 209

^{*} All amounts calculated when framer is pressed are automatically rounded to the number of decimal places specified by the display format. (The display format is described in Section 5.) This rounding affects the number inside the calculator as well as how the number appears in the display. The amounts calculated on your hp 12c may differ from those on the statements of lending institutions by a few cents, since different rounding techniques are sometimes used. To calculate answers rounded to a different number of decimal places, press followed by the number of decimal places desired before you press framer.

Keystrokes	Display	
573.35 CHS PMT	-573.35	Enters PMT (with minus sign for cash paid out).
g END	-573.35	Sets payment mode to End.
12 f AMORT	-6,608.89	Portion of first year's payments (12 months) applied to interest.
[X ≶ Å]	-271.31	Portion of first year's payments applied to principal.
RCL PV	49,728.69	Balance remaining after 1 year.
RCL n	12.00	Total number of payments amortized.

The number of payments keyed in just before f MORT is pressed is taken to be the payments following any that have already been amortized. Thus, if you now press 12 f MORT, your hp 12c will calculate the amounts applied to interest and to the principal from the second year's payments (that is, the second 12 months):

Keystrokes	Display	
12 f AMORT	-6,570.72	Portion of second year's payments applied to interest.
[xey]	-309.48	Portion of second year's payments applied to principal.
$\mathbb{R} \downarrow \mathbb{R} \downarrow$	12.00	Number of payments just amortized.
RCL	49,419.21	Balance remaining after 2 years.
RCL n	24.00	Total number of payments amortized.

Pressing RCL PV or RCL n displays the number in the PV or n register. When you did so after each of the last two calculations, you may have noticed that PV and n had been changed from their original values. The calculator does this so that you can easily check the remaining balance and the total number of payments amortized. But because of this, if you want to generate a new amortization schedule from the beginning, you must reset PV to its original value and reset n to 0.

For example, suppose you now wanted to generate an amortization schedule for each of the first two months:

Keystrokes	Display	Display		
50000 PV	50,000.00	Resets PV to original value.		
0 n	0.00	Resets <i>n</i> to zero.		

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 55 of 209

Keystrokes	Display	
1 f AMORT	-552.08	Portion of first payment applied to interest.
[X ≶ Å]	-21.27	Portion of first payment applied to principal.
1 f AMORT	-551.85	Portion of second payment applied to interest.
x≷y	-21.50	Portion of second payment applied to principal.
RCL n	2.00	Total number of payments amortized.

If you want to generate an amortization schedule but do not already know the monthly payment:

- 1. Calculate PMT as described on page 46.
- 2. Press 0 n to reset *n* to zero.
- 3. Proceed with the amortization procedure listed on page 54 beginning with step 6.

Example: Suppose you obtained a 30-year mortgage instead of a 25-year mortgage for the same principal (\$50,000) and at the same interest rate ($13^{1}/_{4}\%$) as in the preceding example. Calculate the monthly payment, then calculate the amounts applied to interest and to the principal from the first month's payment. Since the interest rate is not being changed, do not press follower. To calculate *PMT*, just enter the new value for n, reset PV, then press PMT.

Keystrokes	Display	
30 g 12x	360.00	Enters n.
50000 PV	50,000.00	Enters PV.
PMT	-562.89	Monthly payment.
0 n	0.00	Resets n to zero.
1 f AMORT	-552.08	Portion of first payment applied to interest.
[X § Y]	-10.81	Portion of first payment applied to principal.
RCL PV	49,989.19	Remaining balance.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 56 of 209


Section 4

Additional Financial Functions

Discounted Cash Flow Analysis: NPV and IRR

The hp 12c provides functions for the two most widely-used methods of discounted cash flow analysis: NPV (net present value) and IRR (internal rate of return). These functions enable you to analyze financial problems involving cash flows (money paid out or received) occurring at regular intervals. As in compound interest calculations, the interval between cash flows can be any time period; however, the amounts of these cash flows need not be equal.

To understand how to use $\overline{\text{NPV}}$ and $\overline{\text{IRR}}$, let's consider the cash flow diagram for an investment that requires an initial cash outlay (CF_0) and generates a cash flow (CF_1) at the end of the first year, and so on up to the final cash flow (CF_0) at the end of the sixth year. In the following diagram, the initial investment is denoted by CF_0 , and is depicted as an arrow pointing down from the time line since it is cash paid out. Cash flows CF_1 and CF_4 also point down from the time line, because they represent projected cash flow losses.



NPV is calculated by adding the initial investment (represented as a negative cash flow) to the present value of the anticipated future cash flows. The interest rate, i, will be referred to in this discussion of NPV and IRR as the rate of return.* The value of NPV indicates the result of the investment:

57

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 57 of 209

^{*} Other terms are sometimes used to refer to the rate of return. These include: required rate of return, minimally acceptable rate of return, and cost of capital.

58 Section 4: Additional Financial Functions

- If NPV is positive, the financial value of the investor's assets would be increased: the investment is financially attractive.
- If NPV is zero, the financial value of the investor's assets would not change: the investor is indifferent toward the investment.
- If NPV is negative, the financial value of the investor's assets would be decreased: the investment is not financially attractive.

A comparison of the *NPV*'s of alternative investment possibilities indicates which of them is most desirable: the greater the *NPV*, the greater the increase in the financial value of the investor's assets.

IRR is the rate of return at which the discounted future cash flows equal the initial cash outlay: IRR is the discount rate at which NPV is zero. The value of IRR relative to the present value discount rate also indicates the result of the investment:

- If IRR is greater than the desired rate of return, the investment is financially attractive.
- If IRR is equal to the desired rate of return, the investor is indifferent toward the investment.
- If IRR is less than the desired rate of return, the investment is not financially attractive.

Calculating Net Present Value (NPV)

Calculating NPV for Ungrouped Cash Flows. If there are no equal consecutive cash flows, use the procedure described (and then summarized) below. With this procedure, NPV (and IRR) problems involving up to 20 cash flows (in addition to the initial investment CF_0) can be solved. If two or more consecutive cash flows are equal — for example, if the cash flows in periods three and four are both \$8,500 — you can solve problems involving more than 20 cash flows, or you can minimize the number of storage registers required for problems involving less than 20 cash flows, by using the procedure described next (under Calculating NPV for Grouped Cash Flows, page 61).

The amount of the initial investment (CF_0) is entered into the calculator using the CFo key. Pressing \mathfrak{g} CFo stores CF_0 in storage register R_0 and also stores the number 0 in the n register.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 58 of 209

The amounts of the subsequent cash flows are stored – in the order they occur – in the remaining storage registers: CF_1 thru CF_9 in R_1 thru R_9 , and CF_{10} thru CF_{19} in $R_{.0}$ thru $R_{.9}$, respectively. If there is a CF_{20} , that amount is stored in the FV register.*

Each cash flow (CF_1 , CF_2 , etc.) is designated CF_p , where j takes on values from 1 up to the number of the final cash flow. The amount of a cash flow is entered using the CF_1 key. Each time CF_2 is pressed, the amount in the display is stored in the next available storage register, and the number in the n register is increased by 1. This register therefore counts how many cash flow amounts (in addition to the initial investment CF_0) have been entered.

Note: When entering cash flow amounts — including the initial investment CF_0 — remember to observe the cash flow sign convention by pressing CHS after keying in a negative cash flow.

In summary, to enter the cash flow amounts:

- 1. Press f CLEAR REG to clear the financial and storage registers.
- 2. Key in the amount of the initial investment, press CHS if that cash flow is negative, then press 9 CFo. If there is no initial investment, press 0 9 CFo.
- 3. Key in the amount of the next cash flow, press CHS if the cash flow is negative, then press 9 CFi. If the cash flow amount is zero in the next period, press 0 9 CFi.
- 4. Repeat step 3 for each cash flow until all have been entered.

With the amounts of the cash flows stored in the calculator's registers, you can calculate NPV as follows:


- 1. Enter the interest rate, using i or 12÷.
- 2. Press f NPV.

The calculated value of *NPV* appears in the display and also is automatically stored in the PV register.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 59 of 209

^{*} If you have stored a program in the calculator, the number of registers available for storing cash flow amounts may be less than 21. (Storage registers are automatically allocated to program lines beginning with $R_{_{9}}$ and proceeding in reverse order to $R_{_{7}}$, as described on pages 93 thru 95.) The maximum number of cash flow amounts (in addition to $CF_{_{0}}$) that can be stored is the number that appears at the right of the display when <code>[9]MEM]</code> is pressed. If the maximum number of cash flow amounts is stored, the final cash flow amount is always stored in the FV register. For example, if <code>MEM]</code> displays **P-08 r-20**, the last cash flow amount that can be stored – $CF_{_{10}}$ – will be stored in FV. Similarly, if <code>MEM]</code> displays **P-22 r-18**, the last cash flow amount that can be stored – $CF_{_{10}}$ – will be stored in FV.

Example: An investor has an opportunity to buy a duplex for \$80,000 and would like a return of at least 13%. He expects to keep the duplex 5 years and then sell it for \$130,000; and he anticipates the cash flows shown in the diagram below. Calculate *NPV* to determine whether the investment would result in a return or a loss.



Note that although a cash flow amount (\$4,500) occurs twice, these cash flows are *not* consecutive. Therefore, these cash flows must be entered using the method described above.

Keystrokes	Display	
f CLEAR REG	0.00	Clears financial and storage registers.
80000 CHS g CFo	-80,000.00	Stores CF_0 (with minus sign for a negative cash flow).
500CHS g CFi	-500.00	Stores CF_1 (with minus sign for a negative cash flow).
4500 g CFi	4,500.00	Stores CF_2 .
5500 g CFi	5,500.00	Stores CF ₃ .
4500 g CFi	4,500.00	Stores CF_4 .
130000 g CF;	130,000.00	Stores CF ₅ .
RCL n	5.00	Checks number of cash flow amounts entered (in addition to $CF_{\scriptscriptstyle 0}$).
13 i	13.00	Stores i.
f NPV	212.18	NPV.

Since NPV is positive, the investment would increase the financial value of the investor's assets.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 60 of 209

Calculating NPV for Grouped Cash Flows. A maximum of 20 cash flow *amounts* (in addition to the initial investment CF_0) can be stored in the hp 12c.* However, problems involving more than 20 cash flows *can* be handled if among the cash flows there are *equal consecutive* cash flows. For such problems, you merely enter along with the amounts of the cash flows the number of times — up to 99 — each amount occurs consecutively. This number is designated N_p corresponding to cash flow *amount* CF_p and is entered using the $\overline{\mathbb{N}}$ key. Each N_j is stored in a special register inside the calculator.

This method can, of course, be used for problems involving fewer than 20 cash flows — and it will require fewer storage registers than the method described above under Calculating *NPV* for Ungrouped Cash Flows. Equal consecutive cash flows can be entered using that method — provided there are enough storage registers available to accommodate the total number of individual cash flows. The facility of grouping equal consecutive cash flows is provided to minimize the number of storage registers required.

Note: When entering cash flow amounts — including the initial investment CF_0 — remember to observe the cash flow sign convention by pressing CHS after keying in the amount for a negative cash flow.

In summary, to enter the amounts of the cash flows and the number of times they occur consecutively:

- 1. Press f CLEARREG to clear the financial and storage registers.
- 2. Key in the amount of the initial investment, press CHS if that cash flow is negative, then press 9 CFo. If there is no initial investment, press 0 9 CFo.
- 3. If the initial investment consists of more than one cash flow of the amount entered in step 2, key in the number of those cash flows, then press $9 \, \text{N}_{\text{i}}$. If $9 \, \text{N}_{\text{i}}$ is not pressed, the calculator assumes that N_0 is 1.
- 4. Key in the amount of the next cash flow, press CHS if that cash flow is negative, then press <code>gCFi</code>. If the cash flow amount is zero in the next period, press <code>OgCFi</code>.
- 5. If the amount entered in step 4 occurs more than once consecutively, key in the number of times that cash flow amount occurs consecutively, then press 9 Nj. If 9 Nj is not pressed, the calculator assumes that Nj is 1 for the CFi just entered.
- 6. Repeat steps 4 and 5 for each CF_i and N_i until all cash flows have been entered.

With the amounts of the cash flows and the number of times they occur consecutively stored in the calculator, *NPV* can be calculated by entering the interest rate and pressing f NPV, just as described earlier.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 61 of 209

^{*} If you have stored a program in the calculator, the number of registers available for storing cash flow amounts may be less than 21.

62 Section 4: Additional Financial Functions

Example: An investor has an opportunity to purchase a piece of property for \$79,000; and he would like a $13^{1}/_{2}\%$ return. He expects to be able to sell it after 10 years for \$100,000 and anticipates the yearly cash flows shown in the table below:

Year	Cash Flow	Year	Cash Flow
1	\$14,000	6	\$9,100
2	\$11,000	7	\$9,000
3	\$10,000	8	\$9,000
4	\$10,000	9	\$4,500
5	\$10,000	10	\$100,000

Since two cash flow amounts (\$10,000 and \$9,000) are repeated consecutively, we can minimize the number of storage registers required by using the method just described.

Keystrokes	Display	
f CLEAR REG	0.00	Clears financial and storage registers.
79000 CHS 9 CFo	-79,000.00	Initial investment (with minus sign for a negative cash flow).
14000 g CFi	14,000.00	First cash flow amount.
11000 g CFi	11,000.00	Next cash flow amount.
10000 g CFi	10,000.00	Next cash flow amount.
3 9 Ni	3.00	Number of times this cash flow amount occurs consecutively.
9100 g CFi	9,100.00	Next cash flow amount.
9000 g CFi	9,000.00	Next cash flow amount.
2 9 N _i	2.00	Number of times this cash flow amount occurs consecutively.
4500 g CFi	4,500.00	Next cash flow amount.
100000 g CFi	100,000.00	Final cash flow amount.
RCL n	7.00	Seven different cash flow amounts have been entered.
13.5 i	13.50	Stores i.
f NPV	907.77	NPV.

Since NPV is positive, the investment would increase the financial value of the investor's assets by \$907.77.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 62 of 209

Calculating Internal Rate of Return (IRR)

- Enter the cash flows using either of the methods described above under Calculating Net Present Value.
- 2. Press f IRR.

The calculated value of *IRR* appears in the display and also is automatically stored in the i register.

Note: Remember that the IRR function may take a significant amount of time to produce an answer, during which the calculator displays **running**.

Example: The NPV calculated in the preceding example was positive, indicating that the actual rate of return (that is, the *IRR*) was greater than the $13^{1}/_{2}$ used in the calculation. Find the *IRR*.

Assuming the cash flows are still stored in the calculator, we need only press

Keystrokes	Display	
f IRR	13.72	IRR is 13 72%

Note that the value calculated by <code>IRR</code> is the *periodic* rate of return. If the cash flow periods are other than years (for example, months or quarters), you can calculate the nominal annual rate of return by multiplying the periodic <code>IRR</code> by the number of periods per year.

As noted above, the calculator may take several seconds or even minutes to produce an answer for *IRR*. This is because the mathematical calculations for finding *IRR* are extremely complex, involving a series of iterations — that is, a series of successive calculations. In each iteration, the calculator uses an estimate of *IRR* as the interest rate in a computation of *NPV*. The iterations are repeated until the computed *NPV* reaches about zero.*

If you do not want to wait for the computation of *IRR* to be completed, press any key. This halts the computation of *IRR* and displays the estimated value of *IRR* being used in the current iteration.† You can then check how good this estimate is by calculating *NPV* using this estimate: if the estimate is close to *IRR*, the *NPV* calculated with it should be close to zero.* The values of *IRR* is put into the i register at the end of each iteration. Therefore, to check how good an estimate of *IRR* is after that estimate is in the display, just press FINPV.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 63 of 209

^{*} In practice, because the complex mathematical calculations inside the calculator are done with numbers rounded to 10 digits, NPV may never reach exactly zero. Nevertheless, the interest rate that results in a very small NPV is very close to the actual IRR.

⁺ Provided the first iteration has been completed.

64 Section 4: Additional Financial Functions

The complex mathematical characteristics of the *IRR* computation have an additional ramification: Depending on the magnitudes and signs of the cash flows, the computation of *IRR* may have a single answer, multiple answers, a negative answer or no answer.*

For additional information regarding IRR, refer to Appendix B. For an alternative method of calculating IRR, refer to Section 13.

Reviewing Cash Flow Entries

- To display a single cash flow amount, press RCL, then key in the number of the register containing the cash flow amount to be displayed. Alternatively, store the number of that cash flow amount (that is, the value of j for the CF_j desired) in the n register, then press RCL 9 CF_j.
- To review all the cash flow amounts, press RCL 9 CF1 repeatedly. This
 displays the cash flow amounts in reverse order that is, beginning with the
 final cash flow and proceeding to CF0.
- To display the number of times a cash flow amount occurs consecutively —
 that is, to display the N_i for a CF_i store the number of that cash flow
 amount (that is, the value of i) in the n register, then press RCL 9 Ni.
- To review all the cash flow amounts together with the number of times each cash flow amount occurs consecutively (that is, to review each CF_j and N_j pair), press RCL 9 NiRCL 9 CF_j repeatedly. This displays N_j followed by CF_j beginning with the final cash flow amount and proceeding to N₀ and CF₀.

Note: Neither \overline{IRR} nor \overline{NPV} change the number in the n register. However, each time \overline{RCL} \overline{g} \overline{CF} is pressed, the number in the n register is decreased by 1. If this is done, or if you manually change the number in the n register in order to display a single N_i and/or CF_{ir} be sure to reset the number in the n register to the total number of cash flow amounts originally entered (not including the amount of the initial investment CF_0). If this is not done, NPV and IRR calculations will give incorrect results; also, a review of cash flow entries would begin with N_n and CF_n , where n is the number currently in the n register.

For example, to display the fifth cash flow amount and the number of times that amount occurs consecutively:

Keystrokes	Display	
RCL 5	9,000.00	CF ₅
5 n	5.00	Stores the value of j in the \mathbf{n} register.

^{*} In the case of multiple answers for IRR, the decision criteria listed on page 57 should be modified accordingly.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 64 of 209

Keystrokes	Display	
RCL g N _j	2.00	N_{5}
7 <u>n</u>	7.00	Resets the number in the ${\bf n}$ register to its original value.

To display all the cash flow amounts and the number of times they occur consecutively:

Keystrokes	Display	
RCL g Ni	1.00	N_7
RCL g CFi	100,000.00	CF ₇
RCL g N _j	1.00	N_{δ}
RCL 9 CFi	4,500.00	CF ₆
RCL g N _j	2.00	$N_{\scriptscriptstyle 5}$
RCL g CFi	9,000.00	CF ₅
•	•	•
•	•	•
•	•	•
RCL g Ni	1.00	N_1
RCL g CFi	14,000.00	CF,
RCL g N _j	1.00	N_o
RCL 9 CF;	-79,000.00	CF_o
7 n	7.00	Resets the number in the ${\bf n}$ register to its original value.

Changing Cash Flow Entries

- To change a cash flow amount:
 - 1. Key the amount into the display.
 - 2. Press STO.
 - 3. Key in the number of the register containing the cash flow amount to be changed.
- To change the number of times a cash flow amount occurs consecutively that is, to change the N_i for a CF_i:
 - 1. Store the number of that cash flow amount (that is, $\it j$) in the $\it n$ register.
 - 2. Key the number of times the cash flow amount occurs consecutively into the display.
 - 3. Press g N_j.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 65 of 209

66 Section 4: Additional Financial Functions

Note: If you change the number in the n register in order to change an N_{ij} be sure to reset the number in the n register to the total number of cash flow amounts originally entered (not including the amount of the initial investment CF_0). If this is not done, NPV and IRR calculations will give incorrect results.

Example 1: With the cash flows now stored in the calculator, change CF_2 from \$11,000 to \$9,000, then calculate the new *NPV* for a $13^1/_2\%$ return.

Keystrokes	Display	
9000 STO 2	9,000.00	Stores the new CF_2 in R_2 .
13.5 i	13.50	Stores i.*
f NPV	-644.75	The new NPV.

Since this *NPV* is negative, the investment would decrease the financial value of the investor's assets.

Example 2: Change N_5 from 2 to 4, then calculate the new *NPV*.

Keystrokes	Display	
5 n	5.00	Stores j in the n register.
4 g N;	4.00	Stores the new N_5 .
7 <u>n</u>	7.00	Resets the number in the n register to its original value.
f NPV	-1,857.21	The new NPV.

Bond Calculations

The hp 12c enables you to solve for bond price (and the interest accrued since the last interest date) and the yield to maturity.† The PRICE and YTM calculations are done assuming a semiannual coupon payment and using an actual/actual basis (such as for U.S. Treasury bonds and U.S. Treasury notes). In accordance with market convention, prices are based on a redemption (par) value of 100.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 66 of 209

^{*} This step is necessary in this example because we have calculated *IRR* since the first time we calculated *NPV*. The *IRR* calculation replaced the 13.5 we keyed into i before calculating *NPV* with the result for *IRR* – 13.72.

[†] All bond calculations are performed in accordance with the Securities Industry Association's recommendations as contained in Spence, Graudenz, and Lynch, Standard Securities Calculation Methods, Securities Industry Association, New York, 1973.

To calculate bond price and yield for a 30/360 bond (that is, using the basis of a 30day month and a 360-day year — such as for municipal bonds, corporate bonds, and state and local government bonds), and to calculate bond price for bonds with an annual coupon payment, refer to Section 16: Bonds.

Bond Price

- 1. Enter the desired yield to maturity (as a percentage), using i.
- 2. Enter the annual coupon rate (as a percentage), using PMT.
- 4. Key in the maturity (redemption) date.
- 5. Press f PRICE

The price is shown in the display and also is stored in the PV register. The interest accrued since the last interest date is held inside the calculator: to display the interest, press [XXY]; to add the interest to the price, press [+].

Example: What price should you pay on April 28, 2004 for a $6^3/_4\%$ U.S. Treasury bond that matures on June 4, 2018, if you want a yield of $8^1/_4\%$. Assume that you normally express dates in the month-day-year format.

Keystrokes	Display	
8.25 i	8.25	Enters yield to maturity.
6.75 PMT	6.75	Enters coupon rate.
g M.DY	6.75	Sets date format to month-day-year.
4.282004 ENTER	4.28	Enters settlement (purchase) date.
6.042018	6.042018	Enters maturity (redemption) date.
f PRICE	87.62	Bond price (as a percent of par).
+	90.31	Total price, including accrued interest.

Bond Yield

- 1. Enter the quoted price (as a percent of par), using PV.
- 2. Enter the annual coupon rate (as a percentage), using PMT.
- 3. Key in the settlement (purchase) date, then press ENTER.
- 4. Key in the maturity (redemption) date.
- 5. Press f YTM.

The yield to maturity is shown in the display and also is stored in the i register.

Note: Remember that the <u>YTM</u> function may take a significant amount of time to produce an answer, during which the calculator displays **running**.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 67 of 209

68 Section 4: Additional Financial Functions

Example: The market is quoting $88^3/_8\%$ for the bond described in the preceding example. What yield will that provide?

Keystrokes	Display	
3ENTER8÷	0.38	Calculates $^3/_8$.
88+PV	88.38	Enters quoted price.
6.75 PMT	6.75	Enters coupon rate.
4.282004 ENTER	4.28	Enters settlement (purchase) date.
6.042018	6.042018	Enters maturity (redemption) date.
f YTM	8.15	Bond yield.

Depreciation Calculations

The hp 12c enables you to calculate depreciation and the remaining depreciable value (book value minus salvage value) using the straight-line, sum-of-the-years-digits, and declining-balance methods. To do so with any of these methods:

- 1. Enter the original cost of the asset, using PV.
- 2. Enter the salvage value of the asset, using $\boxed{\text{FV}}$. If the salvage value is zero, press $\boxed{\text{FV}}$.
- 3. Enter the expected useful life of the asset (in years), using n.
- 4. If the declining-balance method is being used, enter the declining-balance factor (as a percentage), using $\boxed{\text{i}}$. For example, $1^1/_4$ times the straight-line rate 125 percent declining-balance would be entered as 125 $\boxed{\text{i}}$.
- 5. Key in the number of the year for which depreciation is to be calculated.
- 6. Press:
 - f SL for depreciation using the straight-line zsum-p.1(-ths.)5. 6.7(e)TJ 01(e)-1ala-line

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 68 of 209

Example: A metalworking machine, purchased for \$10,000, is depreciated over 5 years. Its salvage value is estimated at \$500. Find the depreciation and remaining depreciable value for the first 3 years of the machine's life using the declining-balance method at double the straight-line rate (200 percent declining-balance).

Keystrokes	Display	
10000 PV	10,000.00	Enters original cost.
500 FV	500.00	Enters salvage value.
5 n	5.00	Enters expected useful life.
200 i	200.00	Enters declining-balance factor.
1 f DB	4,000.00	Depreciation in first year.
[x ≥ y]	5,500.00	Remaining depreciable value after first year.
2fDB	2,400.00	Depreciation in second year.
[X & A]	3,100.00	Remaining depreciable value after second year.
3 f DB	1,440.00	Depreciation in third year.
X≶Ŋ	1,660.00	Remaining depreciable value after third year.

To calculate depreciation and the remaining depreciable value when the acquisition date of the asset does not coincide with the beginning of the fiscal accounting year, refer to the procedures in Section 13. That section also includes a procedure for depreciation calculations when changing from the declining-balance method to the straight-line method, and a procedure for calculating excess depreciation.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 69 of 209

Section 5

Additional Operating Features

Continuous Memory

The calculator's Continuous Memory contains the data storage registers, the financial registers, the stack and LAST X registers, program memory, and status information such as display format, date format, and payment mode. All information in Continuous Memory is preserved even while the calculator is turned off. Furthermore, information in Continuous Memory is preserved for a short time when the batteries are removed, so that you can change the batteries without losing your data and programs.

Continuous Memory may be reset if the calculator is dropped or otherwise traumatized, or if power is interrupted. You can also manually reset Continuous Memory as follows:

- 1. Turn the calculator off.
- 2. Hold down the key, and press ON.

When Continuous Memory is reset:

- All registers are cleared.
- Program memory consists of eight program lines, each containing the instruction 9 GTO 00.
- Display format is set to the standard format with two decimal places.
- Date format is set to month-day-year.
- Payment mode is set to End.

Whenever Continuous Memory has been reset, the display will show **Pr Error**. Pressing any key will clear this message from the display.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 70 of 209

The Display

Status Indicators

Six indicators that appear along the bottom of the display signify the status of the calculator for certain operations. These status indicators are described elsewhere in this handbook where the relevant operation is discussed.


f 9 BEGIN D.MY C PRGM

Number Display Formats

When the calculator is first turned on after coming from the factory or after Continuous Memory has been reset, answers are *displayed* with two decimal places.

Keystrokes	Display
19.8745632ENTER	19.87
5 –	14.87

Although you see only two decimal places, all calculations in your hp 12c are performed with full 10-digit numbers.



When only two decimal places are displayed, numbers are *rounded* to two decimal places: if the third digit is 5 through 9, the second digit is increased by one; if the third digit is 0 through 4, the second digit is not affected. Rounding occurs regardless of how many decimal places are displayed.

Several options are provided for controlling how numbers appear in the display. But regardless of which display format or how many displayed decimal places you specify, the number inside the calculator — which appears altered in the display — is not altered unless you use the RND, AMORT, SL, SOYD, or DB functions.

Standard Display Format. The number 14.87 now in your calculator is currently being displayed in the standard display format with two decimal places shown. To display a different number of decimal places, press f followed by a digit key (0 through 9) specifying the number of decimal places. In the following examples, notice how the displayed form of the number inside the calculator — 14.87456320 — is rounded to the specified number of digits.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 71 of 209

72 Section 5: Additional Operating Features

Keystrokes	Display	
f4	14.8746	
f ₁	14.9	
f ₀	15.	
f 9	14.87456320	Although nine decimal places were specified after f, only eight are displayed since the display can show a total of only 10 digits.

The standard display format, plus the specified number of decimal places, remain in effect until you change them; they are not reset each time the calculator is turned on. However, if Continuous Memory is reset, when the calculator is next turned on numbers will be displayed in the standard display format with two decimal places shown.

If a calculated answer is either too small or too large to be displayed in the standard display format, the display format automatically switches to scientific notation (described below). The display returns to the standard display format for all numbers that can be displayed in that format.

Scientific Notation Display Format



In scientific notation, a number is displayed with its *mantissa* at the left and a two-digit *exponent* at the right. The mantissa is simply the first seven digits in the number, and has a single, nonzero digit to the left of the decimal point. The exponent is simply how many decimal places you would move the decimal point in the mantissa before writing down the number in standard format. If the exponent is negative (that is, there is a minus sign between it and the mantissa), the decimal point should be moved to the left; this occurs for any number less than 1. If the exponent is positive (that is, there is a blank space between it and the mantissa), the decimal point should be moved to the right; this occurs for any number greater than or equal to 1.

To set the display format to scientific notation, press f. For example (assuming the display still shows **14.87456320** from the preceding example):

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 72 of 209

Keystrokes	Display	
f •	1.487456	01

The exponent in this example indicates that the decimal point should be moved one decimal place to the right, giving the number 14.87456, which is the first seven digits of the number previously in the display.

To set the display back to standard display format, press <code>f</code> followed by the desired number of decimal places. Scientific notation display format remains in effect until you change to the standard display format; it is not reset each time the calculator is turned on. However, if Continuous Memory is reset, when the calculator is next turned on the standard display format, with two decimal places, will be used.

Mantissa Display Format. Because both the standard display format and scientific notation display format often show only a few digits of a number, you may occasionally want to see all 10 digits — the full mantissa — of the number inside the calculator. To do so, press fclear fraction and hold down the fraction key. The display will show all 10 digits of the number as long as you hold down the fraction key; after you release the key, the number will again be displayed in the current display format. For instance, if the display still contains the result from the preceding example:

Keystrokes	Display	
f CLEAR PREFIX	1487456320	All 10 digits of the number inside the calculator.
	1.487456 01	Display returns to its former contents when the PREFIX key is released.
f ₂	14.87	Returns display to standard format.

Special Displays

Running. Certain functions and many programs may take several seconds or more to produce an answer. During these calculations, the word **running** flashes in the display to let you know that the calculator is running.

If a calculation results in a number whose magnitude is less than 10^{-99} , the calculation is not halted, but the value 0 is used for that number in subsequent calculations.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 73 of 209

74 Section 5: Additional Operating Features

Errors. If you attempt an improper operation — such as division by zero — the calculator will display the word **Error** followed by a digit (0 through 9). To clear the Error

Page: 74 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Arithmetic Calculations With Constants

Example: At Permex Pipes a certain pipe fitting is packaged in quantities of 15, 75, and 250. If the cost per fitting is \$4.38, calculate the cost of each package.

Keystrokes	Display	
15 ENTER	15.00	Keys first quantity into calculator.
4.38	4.38	Keys unit cost into display.
X	65.70	Cost of a package of 15.
75	75.	Keys second quantity into display.
g LSTx	4.38	Recalls unit cost — which was last number in display before $\boxed{\times}$ was pressed — into display.
X	328.50	Cost of a package of 75.
250	250.	Keys third quantity into display.
g LSTx	4.38	Recalls unit cost into display again.
X	1,095.00	Cost of a package of 250.

Another method for doing arithmetic calculations with constants is described on page 177.

Recovering From Errors in Digit Entry

Example: Suppose you want to divide the total annual production for one of your firm's products (429,000) by the number of retail outlets (987) in order to calculate the average number distributed by each outlet. Unfortunately, you mistakenly key in the number of outlets as 9987 rather than as 987. It's easy to correct:

Keystrokes	Display	
429000 ENTER	429,000.00	
9987	9,987.	You haven't noticed your mistake yet.
÷	42.96	About 43 products per outlet — but that seems too low!
g (LSTX)	9,987.00	Recalls to the display the number that was there before you press ÷. You see that you keyed it in wrong.
429000 ENTER	429,000.00	Begins the problem over.
987÷	434.65	The correct answer.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 75 of 209

Section 6

Statistics Functions

Accumulating Statistics

The hp 12c can perform one- or two-variable statistical calculations. The data is entered into the calculator using the Σ + key, which automatically calculates and stores statistics of the data into storage registers R_1 , through R_δ . (These registers are therefore referred to as the "statistics registers.")

Before beginning to accumulate statistics for a new set of data, you should clear the statistics registers by pressing f clear Σ .*

In one-variable statistical calculations, to enter each data point — referred to as an "x-value" — key the x-value into the display, then press \mathfrak{T} .

In two-variable statistical calculations, to enter each data pair - referred to as the "x and y-values":

- 1. Key the y-value into the display.
- 2. Press ENTER.
- 3. Key the x-value into the display.
- 4. Press Σ +.

Each time you press Σ +, the calculator does the following:

- The number in R_1 is increased by 1, and the result is copied into the display.
- The x-value is added to the number in R₂.
- The square of the x-value is added to the number in R₃.
- The y-value is added to the number in R₄.
- The square of the y-value is added to the number in R₅.
- The product of the x and y-values is added to the number in R_{δ} .

76

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 76 of 209

st This also clears the stack registers and the display.

The table below shows where the accumulated statistics are stored.

Register	Statistic
R ₁ (and display)	n: number of data pairs accumulated.
$R_{\scriptscriptstyle 2}$	Σx: summation of x-values.
R_3	Σx^2 : summation of squares of x-values.
$R_{_4}$	Σy : summation of y-values.
R_5	Σy^2 summation of squares of <i>y-</i> values.
R_6	Σxy : summation of products of x-values and y-values.

Correcting Accumulated Statistics

If you discover you have entered data incorrectly, the accumulated statistics can easily be corrected:

- If the incorrect data point or data pair has just been entered and Σ+ has been pressed, press ¶ LSTX ¶ Σ-.
- If the incorrect data point or data pair is not the most recent one entered, key in the incorrect data point or data pair again as if it were new, but press
 \$\mathbb{T}\$ instead of \$\mathbb{\Sigma}\$.

These operations cancel the effect of the incorrect data point or data pair. You can then enter the data correctly, using Σ +, just as if it were new.

Mean

Pressing \overline{y} \overline{x} calculates the means (arithmetic averages) of the *x-values* (\overline{x}) and of the *y-values* (\overline{y}) . The mean of the *x-values* appears in the display after \overline{x} is pressed; to display the mean of the *y-values*, press $\overline{x \in y}$.

Example: A survey of seven salespersons in your company reveals that they work the following hours a week and sell the following dollar volumes each month. How many hours does the average salesperson work each week? How much does the average salesperson sell each month?

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 77 of 209

78 Section 6: Statistics Functions

Salesperson	Hours/Week	Hours/Week
1	32	\$17,000
2	40	\$25,000
3	45	\$26,000
4	40	\$20,000
5	38	\$21,000
6	50	\$28,000
7	35	\$15,000

To find the average workweek and sales of this sample:

Keystrokes	Display	
	0.00	Clears statistics registers.
32 ENTER 17000 Σ+	32.00 1.00	First entry.
40 ENTER 25000 Σ+	40.00 2.00	Second entry.
45 ENTER 26000 Σ+	45.00 3.00	Third entry.
40 ENTER 20000 Σ+	40.00 4.00	Fourth entry.
38 ENTER 21000 Σ+	38.00 5.00	Fifth entry.
50 ENTER 28000 Σ+	50.00 6.00	Sixth entry.
35 ENTER 15000 Σ+	35.00 7.00	Total number of entries in the sample.
$g\overline{x}$	21,714.29	Mean dollar sales per month $(\frac{1}{X})$.
x≥y	40.00	Mean workweek in hours (\overline{y}) .

Page: 78 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Standard Deviation

Pressing \P s calculates the standard deviation of the *x-values* (s_x) and of the *y-values* (s_y) . (The standard deviation of a set of data is a measure of the dispersion around the mean.) The standard deviation of the *x-values* appears in the display after \P is pressed; to display the standard deviation of the *y-values*, press \P .

Example: To calculate the standard deviations of the *x-values* and of the *y-values* from the preceding example:

Keystrokes	Display	
gs	4,820.59	Standard deviation of sales.
X≷Y	6.03	Standard deviation of hours worked.

The formulas used in the hp 12c for calculating s_x , and s_y give best estimates of the population standard deviation based on a sample of the population. Thus, current statistical convention calls them sample standard deviations. So we have assumed that the seven salespersons are a sample of the population of all salespersons, and our formulas derive best estimates of the population from the sample.

What if the seven salespersons constituted the whole population of salespersons. Then we wouldn't need to *estimate* the *population* standard deviation. We can find the *true population* standard deviation (σ) when the data set equals the total population, using the following keystrokes.*

Keystrokes	Display	
$g\overline{x}$	21,714.29	Mean (dollars)
Σ+	8.00	Number of entries + 1.
gs	4,463.00	$\sigma_{_{x}}$
X ≷ Y	5.58	$\sigma_{_{_{_{_{_{_{_{_{_{_{_{_{_{_{_{_{_{_{$

To continue summing data pairs, press \mathfrak{g} $\overline{\mathfrak{X}}$ \mathfrak{g} Σ - before entering more data.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 79 of 209

^{*} It turns out that if you sum the mean of the population into the set itself and find the new s, computed using the formulas on page 192, that s will be the *population* standard deviation, σ, of the original set.

Linear Estimation

With two-variable statistical data accumulated in the statistics registers, you can estimate a new *y-value* (\hat{y}) given a new *x-value*, and estimate a new *x-value* (\hat{x}) given a new *y-value*.

To calculate \hat{y} :

- 1. Key in a new x-value.
- 2. Press g ŷ,r.

To calculate \hat{x} :

- 1. Key in a new y-value.
- 2. Press g \hat{x} ,r.

Example: Using the accumulated statistics from the preceding problem, estimate the amount of sales delivered by a new salesperson working 48 hours per week.

Display	
28,818.93	Estimated sales for a 48 hour workweek.

The reliability of a linear estimate depends upon how closely the data pairs would, if plotted on a graph, lie in a straight line. The usual measure of this reliability is the correlation coefficient, r. This quantity is automatically calculated whenever \hat{y} or \hat{x} is calculated; to display it, press $x \in \hat{y}$. A correlation coefficient close to 1 or -1 indicates that the data pairs lie very close to a straight line. On the other hand, a correlation coefficient close to 0 indicates that the data pairs do not lie closely to a straight line; and a linear estimate using this data would not be very reliable.

Example: Check the reliability of the linear estimate in the preceding example by displaying the correlation coefficient.

Keystrokes	Display	
[X ≶ Å]	0.90	The correlation coefficient is close to 1, so the sales calculated in the preceding example is a good estimate.

To graph the regression line, calculate the coefficients of the linear equation y = A + Bx.

- 1. Press Ogyr to compute the y-intercept (A).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 80 of 209

Example: Compute the slope and intercept of the regression line in the preceding example.

Keystrokes	Display	
$Og\widehat{y},r$	15.55	y-intercept (A); projected value for $x = 0$.
$1 \ \boxed{g} \ \boxed{\hat{y},r} \ \boxed{x \in y} \ \boxed{R} \ \boxed{x \in y} \ \boxed{-}$	0.001	Slope of the line (B); indicates the change in the projected values caused by an incremental change in the x value.

The equation that describes the regression line is:

$$y = 15.55 + 0.001x$$

Weighted Mean

You can compute the weighted mean of a set of numbers if you know the corresponding weights of the items in question.

- 1. Press f CLEAR Σ .
- 2. Key in the value of the item and press $\overline{\mathbb{NH}}$, then key in its weight and press $\overline{\Sigma^+}$. Key in the second item's value, press $\overline{\mathbb{NH}}$, key in the second weight, and press $\overline{\Sigma^+}$. Continue until you have entered all the values of the items and their corresponding weights. The rule for entering the data is "item $\overline{\mathbb{NH}}$ weight $\overline{\Sigma^+}$."
- 3. Press $\Im \overline{X}_{W}$ to calculate the weighted mean of the items.

Example: Suppose that you stop during a vacation drive to purchase gasoline at four stations as follows: 15 gallons at \$1.16 per gallon, 7 gallons at \$1.24 per gallon, 10 gallons at \$1.20 per gallon, and 17 gallons at \$1.18 per gallon. You want to find the average cost per gallon of gasoline purchased. If you purchased the same quantity at each station, you could determine the simple arithmetic average or mean using the $\overline{\mathbb{X}}$ key. But since you know the value of the item (gasoline) and its corresponding weight (number of gallons purchased), use the $\overline{\mathbb{X}}$ key to find the weighted mean:

Keystrokes	Display	
$\texttt{fCLEAR} \Sigma$	0.00	Clears statistics registers.
1.16 ENTER 15 Σ+	1.00	First item and weight.
$1.24\overline{\text{ENTER}}7\overline{\Sigma}+$	2.00	Second item and weight.
1.20 ENTER 10Σ +	3.00	Third item and weight.
1.18 ENTER 17 Σ+	4.00	Fourth item and weight.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 81 of 209

82 Section 6: Statistics Functions

Keystrokes	Display	
g \overline{X}_{W}	1.19	Weighted mean cost per gallon.

A procedure for calculating the standard deviation and standard error (as well as the mean) of weighted or grouped data is included in the hp 12c Solutions Handbook.

Page: 82 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Section 7

Mathematics and Number-Alteration Functions

The *hp 12c* provides several keys for mathematical functions and for altering, numbers. These functions are useful for specialized financial calculations as well as for general mathematics calculations.

One-Number Functions

Most of the mathematics functions require that only one number be in the calculator (that is, the number in the display) before the function key is pressed. Pressing the function key then replaces the number in the display by the result.

Reciprocal. Pressing $\sqrt[3]{x}$ calculates the reciprocal of the number in the display — that is, it divides 1 by the number in the display.

Square Root. Pressing ① x calculates the square root of the number in the display.

Logarithm. Pressing <code>GLN</code> calculates the natural logarithm (that is, the logarithm to the base e) of the number in the display. To calculate the common logarithm (that is, the logarithm to the base 10) of the number in the display, calculate the natural logarithm, then press <code>10gLN</code> ÷.

Exponential. Pressing $9e^x$ calculates the exponential of the number in the display — that is, it raises the base e to the number in the display.

Factorial. Pressing 9 n! calculates the factorial of the number in the display — that is, it calculates the product of the integers from 1 to n, where n is the number in the display.

Round. The display format specifies to how many decimal places a number inside the calculator is rounded when it appears in the display; but the display format alone does not affect the number itself inside the calculator. Pressing TRND, however, changes the number inside the calculator to match its displayed version. Thus, to round a number in the display to a given number of decimal places, temporarily set the display format (as described on page 71) to show the desired number of decimal places, then press TRND.

Integer. Pressing 9 INTG replaces the number in the display by its integer portion — that is, it replaces each digit to the right of the decimal point by 0. The number is changed inside the calculator as well as in the display. The original number can be recalled to the display by pressing 9 ISTX.

83

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 83 of 209

84 Section 7: Mathematics and Number-Alteration Functions

Fractional. Pressing \P replaces the number in the display by its fractional portion — that is, it replaces all digits to the left of the decimal point by 0. Like \P changes the number inside the calculator as well as its displayed version. The original number can be recalled to the display by pressing \P LSTx.

All of the above functions are used basically in the same way. For example, to find the reciprocal of 0.258:

Keystrokes	Display	
.258	0.258	Keys the number into the display.
1/10	3.88	The reciprocal of 0.258, the original number.

Any of the above functions can be done with a number in the display resulting from a previous calculation, as well as with a number you have just keyed in.

Keystrokes	Display	
f CLEAR PREFIX	3875968992	Displays all 10 digits of the number inside the calculator.
	3.88	Display returns to normal format when PREFIX key is released.
f RND	3.88	The number now in the display appears the same as before, but
f PREFIX	3880000000	Displaying all 10 digits of the number inside the calculator shows RND has changed the number to match its displayed version.
	3.88	Display returns to normal format.
g INTG	3.00	The integer portion of the number previously displayed.
g [LSTx]	3.88	Recalls the original number to the display.
g FRAC	0.88	The fractional portion of the number previously displayed.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 84 of 209

The Power Function

Pressing $\underline{y^x}$ calculates a power of a number — that is, y^x . Like the arithmetic function $\underline{+}$, $\underline{y^x}$ requires two numbers:

- 1. Key in the base number (which is designated by the y on the key).
- 2. Press ENTER to separate the second number (the exponent) from the first (the base).
- 3. Key in the exponent (which is designated by the x on the key).
- 4. Press y^x to calculate the power.

To Calculate	Keystrokes	Display
21.4	2 ENTER 1.4 y^x	2.64
2 ^{-1.4}	$2 \overline{\text{ENTER}} 1.4 \overline{\text{CHS}} \overline{y^x}$	0.38
(-2) ³	2 CHS ENTER 3 y^x	-8.00
$\sqrt[3]{2}$ or $2^{1/3}$	$2\overline{\mathbb{ENTER}}3\overline{y_x}\overline{y^x}$	1.26

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 85 of 209



File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Page: 87 of 209

Dimension: 14.8 cm x 21 cm

Section 8

Programming Basics

Why Use Programs?

A program is simply a sequence of keystrokes that is stored in the calculator. Whenever you have to calculate with the same sequence of keystrokes several times, you can save a great deal of time by incorporating these keystrokes in a program. Instead of pressing all the keys each time, you press just one key to start the program: the calculator does the rest automatically!

Creating a Program

Creating a program consists simply of writing the program, then storing it:

- 1. Write down the sequence of keystrokes that you would use to calculate the quantity or quantities desired.
- Press f P/R to set the calculator to Program mode. When the calculator is
 in Program mode, functions are not executed when they are keyed in, but
 instead are stored inside the calculator. The PRGM status indicator in the
 display is lit when the calculator is in Program mode.
- 3. Press f CLEAR PROM to erase any previous programs that may be stored inside the calculator. If you want to create a new program without erasing a program already stored, skip this step and proceed as described in Section 11, Multiple Programs.
- Key in the sequence of keystrokes that you wrote down in step 1. Skip the beginning keystrokes that enter data, which would differ each time the program is used.

Example: Your office supplies dealer is selling selected stock at 25% off. Create a program that calculates the net cost of an item after the discount is subtracted and the \$5 handling charge is added.

First, we'll manually calculate the net cost of an item listing for \$200.

Keystrokes	Display	
200	200.	Keys in cost of item.
ENTER	200.00	Separates cost of item from percentage to be keyed in next.
25%	50.00	Amount of discount.

88

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 88 of 209

Keystrokes	Display	
	150.00	Price less discount.
5	5.	Handling charge.
+	155.00	Net cost (price less discount plus handling charge).

Next, set the calculator to Program mode and erase any program(s) already stored:

Keystrokes	Display	
f P/R	00-	Sets calculator to Program mode.
f CLEAR PRGM	00-	Clears program(s).

Finally, press the keys that we used above to solve the problem manually. Do not key in 200; this number will vary each time the program is used. Don't be concerned right now about what appears in the display as you press the keys; we'll discuss that later in this section.

Keystrokes	Display	
ENTER	01-	36
2	02-	2
5	03-	5
%	04-	25
	05-	30
5	06-	5
+	07-	40

Running a Program

To run (sometimes called "execute") a program:

- Press f P/R to set the calculator back to Run mode. If the calculator is already in Run mode (that is, the **PRGM** status indicator in the display is not lit), skip this step.
- 2. Key any required data into the calculator, just as if you were calculating manually. When a program is run, it uses the data already keyed into the display and the registers inside the calculator.
- 3. Press $\overline{R/S}$ to begin program execution.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 89 of 209

Example: Run the program created above to calculate the net cost of a typewriter listing for \$625 and an executive chair listing for \$159.

Keystrokes	Display	
f P/R	155.00	Sets calculator to Run mode. Display shows number previously calculated.
625	625.	Keys in price of typewriter.
R/S	473.75	Net cost of typewriter.
159	159.	Keys in list price of chair.
R/S	124.25	Net cost of chair.

That's all there is to creating and running simple programs! But if you want to use programs frequently, you'll want to know more about programming — such as how to check what keystrokes are stored in program memory, how many keystrokes can be stored in program memory, how to correct or otherwise modify programs, how to skip keystrokes when running a program, and so on. Before you can understand these aspects of programming, we need to briefly discuss how keystrokes are treated by the calculator when they are stored in Program mode and when they are executed in Run mode.

Program Memory

Keystrokes entered into the calculator in Program mode are stored in *program memory*. Each digit, decimal point, or function key is called an *instruction* and is stored in one *line* of program memory — usually referred to simply as a *program line*. Keystroke sequences beginning with the f, g, STO, RCL, and GTO prefix keys are considered to comprise a *complete instruction* and are stored in only one program line.

When a program is run, each instruction in program memory is executed — that is, the keystroke in that program line is performed, just as if you were pressing the key manually — beginning with the current line in program memory and proceeding sequentially with the higher-numbered program lines.

Whenever the calculator is in Program mode (that is, whenever the **PRGM** status indicator in the display is lit), the display shows information about the program line to which the calculator is currently set. At the left of the display is the number of the program line within program memory. The remaining digits in the display comprise a code that indicates what instruction has been stored in that program line. No code is shown for program line 00, since no regular instruction is stored there.


File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 90 of 209

Identifying Instructions in Program Lines

Each key on the hp 12c keyboard — except for the digit keys 0 through 9 — is identified by a two-digit "keycode" that corresponds to the key's position on the keyboard. The first digit in the keycode is the number of the key row, counting from row 1 at the top; the second digit is the number of the key in that row, counting from 1 for the first key in the row through 9 for the ninth key in the row and 0 for the tenth key in the row. The keycode for each digit key is simply the digit on the key. Thus, when you keyed the instruction $\frac{\%}{}$ into program memory, the calculator displayed

This indicates that the key for the instruction in program line 04 is in the second row on the keyboard and is the fifth key in that row: the $\frac{1}{2}$ key. When you keyed the instruction $\frac{1}{2}$ into program memory, the calculator displayed

This indicates that the key for the instruction in program line 07 is in the fourth row on the keyboard and is the tenth key in that row: the \pm key. When you keyed the digit 5 into program memory, the keycode displayed was only the digit **5**.



Second row, fifth key

Since keystroke sequences beginning with f, g, gto, gto, gto, and gto are stored in only one program line, the display of that line would show the keycodes for all the keys in the keystroke sequence.

Instruction	Keycode
g \(\DYS \)	nn- 43 26
STO + 1	nn- 44 40 1
g GTO 00	nn- 43,33 00

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 91 of 209

Displaying Program Lines

Pressing f P/R to set the calculator from Run mode to Program mode displays the line number and keycode for the program line to which the calculator is currently set

Occasionally you'll want to check several or all of the instructions stored in program memory. The hp 12c enables you to review program instructions either forward or backward through program memory:

- Pressing SST (single step) while the calculator is in Program mode advances
 the calculator to the next line in program memory, then displays that line
 number and the keycode of the instruction stored there.
- Pressing 9 BST (back step) while the calculator is in Program mode sets the
 calculator back to the previous line in program memory, then displays that
 line number and the keycode of the instruction stored there.

For example, to display the first two lines of the program now stored in program memory, set the calculator to Program mode and press $\overline{\texttt{SST}}$ twice:

Keystrokes	Display		
f P/R	00-		Sets calculator to Program mode and displays current line of program memory
SST	01-	36	Program line 01: ENTER
SST	02-	2	Program line 02: digit 2.

Pressing 9 BST does the reverse:

Keystrokes	Display		
g BST	01-	36	Program line 01.
g BST	00-		Program line 00

If either the <u>SST</u> key or the <u>BST</u> key is held down, the calculator displays *all* of the lines in program memory. Press <u>SST</u> again now, but this time hold it down until program line 07 is displayed.

Keystrokes	Display		
SST	01- 36		Program line 01
	•		•
	•		•
	•		•
(Release SST)	07-	40	Program line 07

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 92 of 209

Program line 07 contains the last instruction *you keyed* into program memory. However, if you press SST again, you'll see that this is *not* the last line *stored* in program memory:

Keystrokes	Display	Display				
SST	08-43, 33	00	Program line 08			

The GTO 00 Instruction and Program Line 00

Whenever you run the program now stored in program memory, the calculator executes the instruction in line 08 after executing the seven instructions you keyed in. This GTO 00 instruction — as its name implies — tells the calculator to "go to" program line 00 and execute the instruction in that line. Although line 00 does not contain a regular instruction, it does contain a "hidden" instruction that tells the calculator to halt program execution. Thus, after each time the program is run, the calculator automatically goes to program line 00 and halts, ready for you to key in new data and run the program again. (The calculator is also automatically set to program line 00 when you press from Program mode to Run mode.)

The \$\text{GTO}\$00 instruction was already stored in line 08 — in fact, in \$all\$ program lines — before you keyed in the program. If no instructions have been keyed into program memory, if Continuous Memory is reset, or if fCLEAR PROM is pressed (in Program mode), the instruction \$\text{GTO}\$00 is automatically stored in program lines 01 through 08. As you key each instruction into program memory, it replaces the \$\text{GTO}\$00 instruction in that program line.

If your program should consist of exactly eight instructions, there would be no GTO 00 instructions remaining at the end of program memory. Nevertheless, after such a program is executed the calculator automatically returns to program line 00 and halts, just as if there were a GTO 00 instruction following the program.

If you key in more than eight instructions, program memory automatically expands to accommodate the additional instructions.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 93 of 209

Expanding Program Memory

If no instructions have been keyed into program memory, if Continuous Memory has been reset, or if fCLEAR PRGM has been pressed (in Program mode), program memory consists of 8 program lines, and there are 20 storage registers available for storage of data. Storage Registers

Program Memory

00	, n	_ n	
01	R_{o}	R _{.0}	
02	R ₁	R .1	
03	R_2	$R_{.2}$	
04	R ₃	R _{.3}	
05	R₄	R _{.4}	
06	R ₅	R.5	
07	R ₆	R _{.6}	
08	R ₇	R _{.7}	
	R_8	R _{.8}	
	Ro	R.	


As you key in a ninth instruction, storage register R $_{\circ}$ is automatically converted into seven new lines of program memory. The instruction you key in is stored in program line 09, and the instruction GTO00 is automatically stored in program lines 10 through 15.

Program Memory Storage Registers \mathbf{R}_{o} 00 01 R_1 02 $R_{.5}$ $R_{.6}$ 09 $R_{.7}$ 10 11 $R_{.8}$ 12 13 14 15

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 94 of 209

Program memory is automatically expanded like this whenever another seven instructions have been keyed into program memory — that is, when you key an instruction into program line 16, 23, 30 etc. In each case, the additional program lines made available are converted, seven lines at a time, from the last available data storage register (whether or not data has been stored in that register; if it has, it will be lost). Furthermore, the six new program lines (following the 16th, 23th etc.) will each contain the instruction GTO00.

To determine at any time how many program lines (including those containing GTO)00) are currently in program memory and how many storage registers are currently available for conversion to program lines or for data storage, press 9 MEM (memory). The calculator will respond with a display like the following:



Up to 99 instructions can be stored in program memory. Doing so would require the conversion of 13 data storage registers (because 99 = 8 + [13 \times 7]), leaving 7 storage registers — R_0 through R_6 — available for data storage.

If you find yourself creating long programs, you should create your programs so that they don't use up program lines unnecessarily, since program memory is limited to 99 program lines. One way to minimize program length is to replace numbers consisting of more than just one digit — like the number 25 in lines 02 and 03 of the program keyed in above — by a RCL instruction, and then storing the number in the designated storage register before running the program. In this case, this would save one program line, since the RCL instruction requires only one program line, not two as are required by the number 25. Of course, doing so uses up data storage registers that you might want to save for other data. As in many business and financial decisions, there is a trade off involved; here it is between program lines and data storage registers.

Setting the Calculator to a Particular Program Line

There will be occasions when you'll want to set the calculator directly to a particular program line — such as when you're storing a second program in program memory or when you're modifying an existing program. Although you can set the calculator to any line by using SST as described above, you can do so more quickly as follows:

With the calculator in Program mode, pressing 9GTO followed by two
digit keys sets the calculator to the program line specified by the digit keys,
and then displays that line number and the keycode of the instruction stored
there.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 95 of 209

 With the calculator in Run mode, pressing graph followed by two digit keys sets the calculator to the program line specified by the digit keys. Since the calculator is not in Program mode, the line number and keycode are not displayed.

The decimal point is not necessary if the calculator is in Run mode, but it is necessary if the calculator is in Program mode.

For example, assuming the calculator is still in Program mode, you can set it to program line 00 as follows:

Keystrokes	Display	
g GTO • 00	00-	Program line 00

Executing a Program One Line at a Time

Pressing SST repeatedly with the calculator in Program mode (as described earlier) enables you to verify that the program you have *stored* is identical to the program you *wrote* — that is, to verify that you have keyed the instructions in correctly. However, this does not ensure that the program you *wrote* calculates the desired results correctly: even programs created by the most experienced programmers often do not work correctly when they are first written.

To help you verify that your program works correctly, you can execute the program one line at a time, using the SST key. Pressing SST while the calculator is in Run mode advances the calculator to the next line in program memory, then displays that line's number and the keycode of the instruction stored there, just as in Program mode. In *Run* mode, however, when the SST key is released the instruction in the program line just displayed is executed and the display then shows the result of executing that line.

For example, to execute the program stored in the calculator one line at a time:

Keystrokes	Display		
f P/R	124.25		Sets calculator to Run mode and to line 00 in program memory. (Display shown assumes results remain from previous calculation.)
625	625.		Keys in price of typewriter.
SST	01-	36	Program line 01: ENTER
	625.00		Result of executing program line 01.
SST	02-	2	Program line 02: 2.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 96 of 209

Keystrokes	Display		
	2.		Result of executing program line 02.
SST	03-	5	Program line 03: 5.
	25.		Result of executing program line 03.
SST	04-	25	Program line 04: %
	156.25		Result of executing program line 04.
SST	05-	30	Program line 05: $\overline{}$
	468.75		Result of executing program line 05.
SST	06-	5	Program line 06: 5
	5.		Result of executing program line 06.
SST	07-	40	Program line 07: \pm
	473.75		Result of executing program line 07 (the last line of the program).

Pressing <code>@_BST</code> while the calculator is in Run mode sets the calculator to the previous line in program memory, then displays that line's number and the keycode of the instruction stored there, just as in Program mode. In Run mode, however, when the <code>BST</code> key is released the display again shows the same number as it did before <code>@_BST</code> was pressed: no instruction in program memory is executed.

Interrupting Program Execution

Occasionally you'll want a program to stop executing so that you can see an intermediate result or enter new data. The hp 12c provides two functions for doing so: PSE (pause) and R/S (run/stop).

Pausing During Program Execution

When a running program executes a PSE instruction, program execution halts for about 1 second, then resumes. During the pause, the calculator displays the last result calculated before the PSE instruction was executed.

If you press any key during a pause, program execution is halted indefinitely. To resume program execution at the program line following that containing the $\overline{\text{PSE}}$ instruction, press $\overline{\text{R/S}}$.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 97 of 209

Example: Create a program that calculates the entries in the AMOUNT, TAX, and TOTAL columns for each item on the jewelry distributor's invoice shown on the next page, and also calculates the total in each of these columns for all items on the invoice. Assume the sales tax is $6^3/_4\%$.

DIRECT FORM PURCHASE REQUISITION ORDER P.O. No. 25-								
					RA	-	GER, BEN EWELERS	TZ & YATES
-				- -		New York	/. Morrison k, New York ne (716) 731	, 14203
	ORDER DATE	CC	CONFIRMING		HIP VIA: SU	-		
	ITEM	QTY. DESCRIPTION			UNIT PRICE	AMOUNT	TAX 6.75%	TOTAL
	1	13	SS4 Star Sapph	iire	\$68.50	?	?	?
	2	18	RG13 Ruby Ring	9	72.90	?	?	?
	3	24	GB87 Gold Ban	d 	85.00	?	?	?
	4	5	DG163 Diamon	DG163 Diamond		?	?	?
	5							

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 98 of 209

Pressing the <code>9</code> PSE keys is not necessary when we do the calculations manually, since in Run mode the result of every intermediate calculation is displayed automatically; but we'll include PSE instructions in the program so that the intermediate results AMOUNT and TAX are automatically displayed when the program is executed.

Keystrokes	Display	
6.75STO0	6.75	Stores tax rate in R_0 .
f CLEAR Σ	0.00	Clears the registers in $R_{_{1}}$ through $R_{_{\delta}}.$
13	13.	Keys in quantity of item.
ENTER	13.00	Separates quantity of item from cost of item to be keyed in next.
68.5	68.5	Keys in cost of item.
X	890.50	AMOUNT.
STO + 1	890.50	Adds AMOUNT to sum of AMOUNT entries in register R_1 .
RCL 0	6.75	Recalls tax rate to display.
%	60.11	TAX.
STO +2	60.11	Adds TAX to sum of TAX entries in register ${\rm R_2}.$
+	950.61	TOTAL.
STO +3	950.61	Adds TOTAL to sum of TOTAL entries in register $\rm R_{\rm 3}$.

Now, we'll store the program in program memory. Do not key in the quantity and cost of each item; these numbers will vary each time the program is run.

Keystrokes	Display	
f P/R	OO – Sets calculator to Program mode.	1
f CLEAR PRGM	00- Clears program memory.	
X	01- 20	
g PSE	02- 43 31 Pauses to display AMOUI	NT.
STO + 1	03- 44 40 1	
RCL 0	04- 45 0	
%	05- 25	

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 99 of 209

Keystrokes

Display

reysii okes	Dispi	۰,			
g PSE	06-		43	31	Pauses to display TAX.
STO +2	07-	44	40	2	
+	-80			40	
STO+3	09-	44	40	3	
Now, to run the program:					
Keystrokes	Displ	ay			
f P/R	950.	61			Sets calculator to Run mode.
f CLEAR Σ	0.00				Clears registers R ₁ - R ₆ .
6.75STO0					Stores tax rate.
13EMER68.5	68.5				Enters quantity and price of first item on invoice.
R/S	890.	50			AMOUNT for first item.
	60.1	1			TAX for first item.
	950.	61			TOTAL for first item.
18ENTER 72.9	72.9				Enters quantity and price of second item on invoice.
R/S	1,31	2.2	0		AMOUNT for second item.
	88.5	7			TAX for second item.
	1,40	0.7	7		TOTAL for second item.
24 ENTER 85	85.				Enters quantity and price of third item on invoice.
R/S	2,04	0.0	0		AMOUNT for third item.
	137.	70			TAX for third item.
	2,17	7.7	0		TOTAL for third item.
5 ENTER 345	345.				Enters quantity and price of fourth item on invoice.
R/S	1,72	5.0	0		AMOUNT for fourth item.
	116.	44			TAX for fourth item.
	1,84	1.4	4		TOTAL for fourth item.
RCL 1	5,96	7.7	0		Sum of AMOUNT column.
RCL 2	402.	82			Sum of TAX column.
RCL 3	6,37	0.5	2		Sum of TOTAL column.

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Page: 100 of 209

Dimension: 14.8 cm x 21 cm

If the duration of the pause is not long enough to write down the number displayed, you can prolong it by using more than one PSE instruction. Alternatively, you can have the program automatically *stop* as described next.

Stopping Program Execution

Stopping Program Execution Automatically. Program execution is automatically halted when the program executes a $\overline{R/S}$ instruction. To resume executing the program from the program line at which execution was halted, press $\overline{R/S}$.

Example: Replace the program above by one containing $\overline{R/S}$ instructions instead of \overline{PSE} instructions.

Display			
00-			Sets calculator to Program mode.
00-			Clears program memory.
01-		20	
02-		31	Stops program execution to display AMOUNT.
03- 44	40	1	
04-	45	0	
05-		25	
06-		31	Stops program execution to display TAX.
07- 44	40	2	
08-		40	
09- 44	40	3	
6,370.5	52		Sets calculator to Run mode.
0.00			Clears registers R_1 through R_6 .
68.5			First item.
890.50			AMOUNT for first item.
60.11			TAX for first item.
950.61			TOTAL for first item.
72.9			Second item.
1,312.2	20		AMOUNT for second item.
88.57			TAX for second item.
1,400.7	17		TOTAL for second item.
	00- 00- 01- 02- 03- 44 04- 05- 06- 07- 44 08- 09- 44 6,370.5 0.00 68.5 890.50 60.11 950.61 72.9 1,312.2	00- 00- 01- 02- 03-44 40 04- 45 05- 06- 07-44 40 08- 09-44 40 6,370.52 0.00 68.5 890.50 60.11 950.61 72.9 1,312.20	00- 00- 01- 20 02- 31 03-44 40 1 04- 45 0 05- 25 06- 31 07-44 40 2 08- 40 09-44 40 3 6,370.52 0.00 68.5 890.50 60.11 950.61 72.9 1,312.20 88.57

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 101 of 209

Keystrokes	Display	
24 ENTER 85	85.	Third item.
R/S	2,040.00	AMOUNT for third item.
R/S	137.70	TAX for third item.
R/S	2,177.70	TOTAL for third item.
5 ENTER 345	345.	Fourth item.
R/S	1,725.00	AMOUNT for fourth item.
R/S	116.44	TAX for fourth item.
R/S	1,841.44	TOTAL for fourth item.
RCL 1	5,967.70	Sum of AMOUNT column.
RCL 2	402.82	Sum of TAX column.
RCL 3	6,370.52	Sum of TOTAL column.

Program execution is also automatically halted when the calculator overflows (refer to page 73) or attempts an improper operation that results in an **Error** display. Either of these conditions signifies that the program itself probably contains an error

To determine at which program line execution has halted (in order to locate the error), press any key to clear the **Error** display, then press fp/R to set the calculator to Program mode and display that program line.

You may also want to display the current program line (by pressing f P/R) if your program has halted at one of several R/S instructions in your program and you want to determine which one that is. To continue executing the program afterward:

- 1. Press f P/R to set the calculator back to Run mode.
- 2. If you want to resume execution from the program line at which execution halted rather than from line 00, press 9]GTO followed by two digit keys that specify the program line desired.
- 3. Press R/S to resume execution.

Stopping Program Execution Manually. Pressing any key while a program is running halts program execution. You may want to do this if the calculated results displayed by a running program appear to be incorrect (indicating that the program itself is incorrect).

To halt program execution during a pause in a running program (that is, when PSE is executed), press any key.

After stopping program execution manually, you can determine at which program line execution has halted and/or resume program execution as described above.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 102 of 209


Section 9

Branching and Looping

Although the instructions in a program normally are executed in order of their program line numbers, in some situations it is desirable to have program execution transfer or "branch" to a program line that is not the next line in program memory. Branching also makes it possible to automatically execute portions of a program more than once — a process called "looping."

Simple Branching

The GTO (go to) instruction is used in a program to transfer execution to any program line. The program line desired is specified by keying its two-digit line number into the program line containing the GTO instruction. When the GTO instruction is executed, program execution branches or "goes to" the program line specified and then continues sequentially as usual.



You have already seen a common use of branching: the $\overline{\text{GTO}}$ 00 instruction (that is stored in program memory after the program you key in) transfers execution to program line 00. A $\overline{\text{GTO}}$ instruction can be used to branch not only backward in program memory — as in the case of $\overline{\text{GTO}}$ 00 and as illustrated above — but also forward in program memory. Backward branching is typically done to create loops (as described next); forward branching is typically done in conjunction with an $\overline{\text{xsy}}$ or $\overline{\text{x=0}}$ instruction for conditional branching (as described afterward).

103

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 103 of 209

104 Section 9: Branching and Looping

Looping

If a GTO instruction specifies a lower-numbered line in program memory, the instructions in the program lines between the specified line and the GTO instruction will be executed repeatedly. As can be seen in the illustration above under Simple Branching, once the program begins executing the "loop" it will execute it again and again.

If you want to terminate the execution of a loop, you can include an $x \in Y$ or x = 0 instruction (described below) or an $x \in Y$ instruction within the loop. You can also terminate execution by pressing any key while the loop is being executed.

Example: The following program automatically amortizes the payments on a home mortgage without requiring you to press f MANORT for each payment. It will amortize one month's payments each time or one year's payments each time the loop is executed, depending on whether the number 1 or 12 is in the display when you start running the program. Before running the program, we'll "initialize" it by storing the required data in the financial registers — just as we would do if we were amortizing a single payment manually. We'll run the program for a \$50,000 mortgage at $12^3/_4\%$ for 30 years, and we'll key 1 into the display just before running it in order to amortize monthly payments. For the first two "passes" through the loop we'll execute the program one line at a time, using SST, so that we can see the looping occurring; then we'll use R/S to execute the entire loop a third time before terminating execution.

Keystrokes	Display		
f P/R	00-		Sets calculator to Program mode.
f CLEAR PRGM	00-		Clears program memory
STO 0	01-	44	O Stores the number from the display into register $R_{\rm o}$. This number will be the number of payments to be amortized.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 104 of 209

ince_0	V-		·	be amortized. This program line is the one to which program execution will later branch. It is included because after the first time the loop is executed, the number in the "display"* is replaced by the result of MORT.
f AMORT	03-	42	11	Amortizes payment(s).
g PSE	04-	43	31	Pauses to display amount of payment(s) applied to interest.
X ≥ Y	05-		34	Brings amount of payment(s) applied to principal into "display."*
9 PSE	06-	43	31	Pauses to display amount of payment(s) applied to principal.
9 БТО 02	07-43,	33	02	Transfers program execution to line 02, so that the number of payments to be amortized can be recalled to the display before the AMORT instruction in line 03 is executed.
f P/R	0.00			Sets calculator to Run mode. (Display shown assumes no results remain from previous calculations.)
f CLEAR FIN	0.00			Clears financial registers.
30 g 12x	360.00			Enters n.
12.75g12÷	1.06			Enters i.
50000 PV	50,000.	00		Enters PV.
g END	50,000.	00		Sets payment to End.
PMT	-543.35			Calculates the monthly payment.
0 n	0.00			Reset <i>n</i> to zero.
1	1.			Keys 1 into the display to amortize monthly payments.
SST	01-	44	0	Line 01: STO 0.
	1.00			

 $^{\ ^{*}}$ More precisely, the number in the X-register.

Keystrokes

RCL 0

Display 02-

45

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Page: 105 of 209

Dimension: 14.8 cm x 21 cm

106 Section 9: Branching and Looping

Keystrokes	Display			
SST	02-	45	0	Line 02: RCL 0. This is the beginning of the first pass through the loop.
	1.00			
SST	03-	42	11	Line 03: f AMORT.
	-531.25	i		Portion of first month's payment applied to interest.
SST	04-	43	31	Line 04: 9 PSE.
	-531.25	;		
SST	05-		34	Line 05: [X≷Y].
	-12.10			Portion of first month's payment applied to principal.
SST	06-	43	31	Line 06: 9 PSE.
	-12.10			
SST	07-43,	33	02	Line 07: 9GTO02. This is the end of the first pass through the loop.
	-12.10			
SST	02-	45	0	Line 02: RCL 0. Program execution has branched to the beginning of the loop for the second pass through it.
	1.00			
SST	03-	42	11	Line 03: f AMORT.
	-531.12	!		Portion of second month's payment applied to interest.
SST	04-	43	31	Line 04: 9 PSE.
	-531.12	!		
SST	05-		34	Line 05: [X≷Y].
	-12.23			Portion of second month's payment applied to principal.
SST	06-	43	31	Line 06: 9 PSE.
	-12.23			

Page: 106 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Keystrokes	Display	
SST	07-43, 33	02 Line 07: 9GTO02. This is the end of the second pass through the loop.
	-12.23	
R/S	-530.99	Portion of third month's payment applied to interest.
	-12.36	Portion of third month's payment applied to principal.
R/S (or any key)	-12.36	Halts program execution.

Conditional Branching

Often there are situations when it is desirable for a program to be able to branch to different lines in program memory, depending on certain conditions. For example, a program used by an accountant to calculate taxes might need to branch to different program lines depending on the tax rate for the particular income level.

The hp 12c provides two *conditional* test instructions that are used in programs for conditional branching:

- XKY tests whether the number in the X-register (represented by the x in the key symbol) is less than or equal to the number in the Y-register (represented by the y in the key symbol). As discussed in Appendix A, the number in the X-register is simply the number that would, if the calculator were in Run mode, be currently in the display; and the number in the Y-register is the number that would, if the calculator were in Run mode, have been in the display when WIE was pressed. For example, pressing 4 WIE 5 would place the number 4 in the Y-register and the number 5 in the X-register.
- x=0 tests whether the number in the X-register is equal to zero.


The possible results of executing either of these instructions are:

- If the condition tested for is true when the instruction is executed, program execution continues sequentially with the instruction in the next line of program memory.
- If the condition tested for is false when the instruction is executed, program
 execution skips the instruction in the next line of program memory and
 continues with the instruction in the following line.


These rules can be summarized as "DO if TRUE".

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 107 of 209


108 Section 9: Branching and Looping



The program line immediately following that containing the conditional test instruction can contain any instruction; however, the most commonly used instruction there is GTO. If a GTO instruction follows a conditional test instruction, program execution branches elsewhere in program memory if the condition is true and continues with the next line in program memory if the condition is false.



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 108 of 209



Y —	income	income	income	income
x —	25.00	25.00	20.00	tax
Keys –	RCL 2	GTO 08	RCL 1	%
Line —	05	06	07	08

We'll key the income into the display before running the program so that it will be in the X-register when the RCLO instruction in program line 01 is executed. This instruction will place the test value 20,000 in the X-register and (as explained in Appendix A) move the income into the Y-register. The $\boxed{x \nmid y}$ instruction in program line 02 will exchange the numbers in the X- and Y-registers (as also explained in Appendix A): that is, it will place the income back into the X-register and place the test value into the Y-register. This is necessary because when either the \boxed{RCL} 2 instruction in line 05 or the \boxed{RCL} 1 instruction in line 07 is executed, the number in the X-register is moved into the Y-register; if the $\boxed{x \nmid y}$ instruction were not included, the test value 20,000, rather than the income, would be in the Y-register when the \boxed{w} instruction in line 08 is executed.

Keystrokes	Display			
f P/R	07- 43,	33	02	Sets calculator to Program mode. (Display shows program line at which execution was halted at end of preceding example.)
f CLEAR PRGM	00-			Clears program memory.
RCL 0	01-	45	0	Recalls test value into X-register and places income in Y-register.
X ≥ Y	02-		34	Places income in X-register and test value in Y-register.
g x≤y	03-	43	34	Tests whether number in X-register (income) is less than or equal to number in Y-register (20,000).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 109 of 209

110 Section 9: Branching and Looping

Keystrokes	Display			
g GTO 07	04-43,	33	07	If condition is true, branches to program line 07.
RCL 2	05-	45	2	If condition is false, recalls 25% tax rate to X-register.
9 GTO 08	06-43,	33	80	Branches to program line 08.
RCL 1	07-	45	1	Recalls 20% tax rate to X-register.
%	-80		25	Calculates tax.
f P/R	-12.36			Sets calculator to Run mode. (Display shows results of running of previous program.)

Now, we'll store the required numbers in registers $R_{\rm D}$, $R_{\rm 1}$, and $R_{\rm 2}$, then we'll run the program, using SST so that we can check that the branching occurs properly. It's good practice with programs containing conditional test instructions to check that the program branches correctly for all possible conditions: in this case, if the income is less than, equal to, or greater than the test value.

Keystrokes	Display		
20000 <u>sto</u> 0	20,000.00	Stores test value in register R _o .	
20STO 1	20.00	Stores 20% tax rate in register R ₁ .	
25STO 2	25.00	Stores 25% tax rate in register R_2 .	
15000	15,000.	Keys income less than test value into display and X-register.	
SST	01- 45 0	Line 01: RCL 0.	
	20,000.00	Test value has been recalled to X-register, moving income to Y-register.	
SST	02- 34	Line 02: [X≷Y]	
	15,000.00	Income has been placed in X-register and test value has been placed in Y-register.	
SST	03- 43 34	Line 03: g x sy	
	15,000.00		
SST	04-43, 33 07	Condition tested by Key was true, so program execution continued with line 04: 9 GTO 07.	

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 110 of 209

X-register, moving income to

Y-register.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 111 of 209

112 Section 9: Branching and Looping

Keystrokes	Display		
SST	02-	34	Line 02: [X≷Y].
	25,000.00		Income has been placed in X-register and test value has been placed in Y-register.
SST	03- 43	34	Line 03: 9 x y.
	25,000.00		
SST	05- 45	2	Condition tested by X <y 05:="" 2.<="" and="" at="" continued="" execution="" false,="" line="" next="" program="" rcl="" skipped="" so="" td="" the="" was=""></y>
	25.00		25% tax rate has been recalled to X-register, moving income to Y-register.
SST	06-43, 33	08	Line 06: 9 GTO 08.
	25.00		
SST	08-	25	Line 08: %.
	6,250.00		25% of $25,000 = 6,250$.

Page: 112 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Section 10

Program Editing

There are various reasons why you might want to modify a program you have stored in Program memory: to correct a program that turns out to have errors; to insert new instructions such as $\overline{\text{STO}}$ to store intermediate results or $\overline{\text{PSE}}$ to display intermediate results; or to replace a $\overline{\text{PSE}}$ instruction by an $\overline{\text{R/S}}$ instruction.

Rather than clearing program memory and keying in the modified program, you can modify the program already stored in the calculator. This is called *program editing*.

Changing the Instruction in a Program Line

To change a single instruction in program memory:

- 1. Press f P/R to set the calculator to Program mode.
- 2. Use SST, BST, or GTO to set the calculator to the program line preceding the line containing the instruction to be changed.
- 3. Key in the new instruction.

For example, to change the instruction stored in program line 05, press <code>9GTO</code> •04, then key in the new instruction that is to be stored in program line 05. The instruction previously stored in line 05 will be replaced; it is *not* automatically "bumped" into line 06.

Example: With the last program from the preceding section still stored in the calculator, suppose you wanted to use register R_2 for some other purpose, and so you needed to replace the RCL = 1 instruction in program line 05 with, say, RCL = 1 of RCL = 1

Keystrokes	Display		
f P/R	00-		Sets calculator to Program mode.
9 GTO • 04	04-43, 33	07	Sets calculator to program line preceding that containing the instruction to be changed.
RCL 6	05- 45	6	Keys new instruction into program line 05, replacing the RCL 2 instruction previously there.
SST	06-43, 33	80	Shows that instruction in program line 06 has not been changed.

113

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 113 of 209

Adding Instructions Within a Program

If an instruction is to be added within a program, simply keying it in will replace the instruction previously stored in that program line, as described above; the contents of all higher-numbered program lines remain unchanged.

To add instructions within a program, you could simply key in the new instructions, beginning at the proper program line, followed by the original instructions from that program line through the end of the program. This method is described below under Adding Instructions by Replacement. When instructions must be added in the middle of a long program, however, using this method will require you to key in numerous instructions — namely, the original instructions from the point at which the new instructions are added through the end of program memory. Since keying in these instructions may require a significant amount of time, in such situations you may prefer to use the method described below under Adding Instructions by Branching.

That method basically involves branching to the new instructions which are stored at the end of program memory, then branching back to the program line immediately following the line from which you branched out. Adding instructions by branching is not so simple as adding instructions by replacement; however, it generally will require fewer keystrokes whenever there are more than four program lines between (and including) the first line to be executed after the new instruction(s) and the last line you keyed into program memory. Furthermore, if program memory includes branches to program lines following the point at which the new instruction(s) are being added, adding instructions by branching will *not* require that you change the line numbers specified in the GTO instructions, which *may* be necessary when you add instructions by replacement.

Adding Instructions by Replacement

- 1. Press f P/R to set the calculator to Program mode.
- 2. Press @GTO followed by two digits that specify the last program line to be executed before the added instruction(s). This sets the calculator to the proper program line for adding the new instruction(s) in the next step.
- 3. Key in the new instruction or instructions.
- 4. Key in the original instruction or instructions, beginning with the first instruction to be executed *after* the added instruction(s), and continuing through the last instruction you keyed into program memory.

Note: If program memory includes branches to program lines following that at which the first new instruction is being added, remember to change the line number(s) specified in the GTO instruction(s) — as described above under Changing the Instruction in a Program Line — to the actual *new* line number(s).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 115 of 209

116 Section 10: Program Editing

Example: Assuming you have added a $\overline{}$ instruction at the end of program memory as in the preceding example, suppose you now wanted to insert an $\overline{R/S}$ instruction before the $\overline{}$ instruction so that the program will display the amount of the tax before displaying the net income after tax. Since there is only one instruction ($\overline{}$) following the point at which the new instruction is being added, it is simplest to add the $\overline{R/S}$ instruction by replacement, as follows:

Keystrokes	Display		
f P/R	00-		Sets calculator to Program mode.
g GTO • 08	08-	25	Sets calculator to last program line to be executed, which contains the instruction.
R/S	09-	31	Keys in new instruction.
-	10-	30	Keys in original instruction, which was replaced by new instruction added.
f P/R	12,000.00		Sets calculator back to Run mode.
15000R/S	3,000.00		Twenty percent tax on \$15,000 income.
R/S	12,000.00		Net income after tax.

Adding Instructions by Branching

- 1. Press f P/R to set the calculator to Program mode.
- 2. Press 9GTO followed by two digits that specify the program line immediately preceding the point at which the new instruction(s) are being added usually, the last program line to be executed before the added instruction(s). This sets the calculator to the proper program line for inserting a GTO instruction in the next step. This GTO instruction will replace whatever instruction was already stored there, but that instruction will be keyed back into program memory, to be executed just after the new instructions, in step
- 3. Press 9 CTO followed by two digits that specify the second line after the last line you keyed into program memory. (Branching to the second line rather than to the first is necessary because the first line following the last program in program memory must contain a GTO00 instruction. The GTO00 instruction ensures that program execution will branch to line 00 and halt after the program is run.) For example, if the last line you keyed into program memory was line 10, you would press 9 GTO12 at this step, preserving the 9 GTO00 in line 11.
- Press 9 GTO followed by two digits that specify the last line you keyed into program memory.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 116 of 209

- 5. Press 9 GTO 00. This automatically converts a data storage register into seven additional lines of program memory (if there was not already a GTO 00 instruction remaining at the end of program memory), and it ensures that program execution will branch to line 00 after the program is run.
- 6. Key in the instruction(s) being added.
- 7. Key in the instruction that originally immediately followed the point at which the new instruction(s) are being added that is, the first instruction to be executed after the added instruction(s). (This instruction was replaced by the GTO instruction keyed in at step 3.)
- 8. Press 9 GTO followed by two digits that specify the *second* line following the point at which the new instruction(s) are being added. This GTO instruction will cause program execution to branch back to the proper line within the original program.

Example: Continuing with the preceding example, suppose incomes less than or equal to \$7,500 were not to be taxed. You could modify the program to check for this condition and stop at line 00, displaying the original income keyed in, by storing 7,500 in register R₃ and adding the following instructions between lines 00 and 01: RCL3[XEY] 9 INSTITUTE [STORT OF THE RECLARCE OF T

Keystrokes	Display	
f P/R	00-	Sets calculator to Program mode.
ggro•00	00-	Sets calculator to program line immediately preceding point at which new instructions are being added. (In this particular example, this step could have been skipped since calculator was already set at the proper program line.)
9 GTO 12	01-43, 33 12	Branches to program line 12, the second line after last line of program.
ggro•10	10- 30	Sets calculator to last line of program so that GTO 00 instruction keyed in next will be stored in first line following program.
9 GTO 00	11-43, 33 00	Ensures that GTO 00 instruction follows program.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 117 of 209


118 Section 10: Program Editing

Keystrokes	Display		
RCL 3	12- 45	3	1
X≷Y	13-	34	
g x≤y	14- 43	34	Added instructions.
g GTO OO	15-43, 33	00	
RCL O	16- 45	0	Keys in instruction immediately following point at which new instructions are being added. (This instruction was replaced in line 01 by GTO 12 instruction.)
g GTO 02	17-43, 33	02	Branches back to second line (line 02) following point at which new instructions are being added.
f P/R	12,000.00		Sets calculator back to Run mode.
7500STO3	7,500.00		Stores test value in register R ₃ .
6500 _{R/S}	6,500.00		Runs program for income less than \$7,500. Display shows original income keyed in, indicating that tax r0.0013 Tc0.002 Tw

Page: 118 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Section 10: Program Editing 119



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 119 of 209

Section 11

Multiple Programs

You can store multiple programs in program memory, provided that you separate them by instructions that will halt program execution after each program is run and return to the beginning of the program if it is run again. You can run programs after the first one stored in program memory by setting the calculator to the first line of the program using GTO before pressing R/S.

Storing Another Program

To store a program after another program is already stored in program memory:

- Press f P/R to set the calculator to Program mode. Do not clear program memory.
- 2. Press <code>g_GTO</code> followed by two digits that specify the number of the last line you keyed into program memory.

Note: If this is the second program to be stored in program memory, you will need to ensure that a GTO 00 instruction separates it from the first program by doing step 3. If there are already two or more programs stored in program memory, skip step 3 and proceed with step 4.

- 3. Press 9 GTO 00. This automatically converts a data storage register into seven additional lines of program memory (if there was not already a GTO 00 instruction remaining at the end of program memory), and it ensures that program execution will branch to line 00 after the first program is run.
- 4. Key the program into program memory. If you are storing a program that you originally had written to be stored at the beginning of program memory and the program contains a GTO instruction, be sure to change the line number specified in the instruction so that the program will branch to the actual new line number.

Note: The next two steps are included so that program execution will halt after this program is run and will return to the beginning of the program if it is run again. If the program ends with a loop, you should skip steps 5 and 6 since the instructions in those steps would serve no purpose and never be executed.

- 5. Press $\overline{\text{R/S}}$. This halts program execution at the end of the program.
- 6. Press 9 GTO followed by two digit keys that specify the first line number of your new program. This transfers program execution to the beginning of the new program when the program is run again.

120

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 120 of 209

Example 1: Assuming that program memory still contains the last program from the preceding section (which consisted of 17 program lines), store after that program the office-supplies program from Section 8 (page 88). Since this is the second program to be stored in program memory, we'll ensure that a $\underline{\texttt{GTO}} 00$ instruction separates it from the first program by doing step 3 in the procedure above. Furthermore, since this program does not end with a loop, we'll do steps 5 and 6 too.

Keystrokes	Display		
f P/R	00-		Sets calculator to Program mode.
9 GTO • 17	17-43, 33	02	Sets calculator to last line keyed into program memory.
g GTO 00	18-43, 33	00	Ensures that second program is separated from first by GTO 00.
ENTER	19-	36	1
2	20-	2	
5	21-	5	
%	22-	25	Keys in program.
_	23-	30	
5	24-	5	
+	25-	40	J
R/S	26-	31	Halts program execution.
g GTO 19	27-43, 33	19	Branches to beginning of program.
f P/R	12,000.00		Sets calculator back to Run mode. (Display shown assumes results remain from running program in previous example.)

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 121 of 209

122 Section 11: Multiple Programs

Example 2: With the two programs now stored in program memory from the preceding examples (occupying 27 program lines), store the amortization program from Section 9(page 103). Since there are already two programs stored in program memory, we'll skip step 3 in the procedure above. Furthermore, since the amortization program ends with a loop, we'll skip steps 5 and 6. When the amortization program was stored at the beginning of program memory, the GTO instruction at the end of the program branched to the RCLO instruction in line 02. Since the RCLO instruction is now in line 29, we'll specify that line number with the GTO instruction in line 34.

Keystrokes	Display				
f P/R	00-				ets calculator to Program ode.
9 GTO • 27	27- 43,	33	19		ets calculator to last line keyed to program memory.
STO 0	28-	44	0	٦	
RCL 0	29-	45	0		
f AMORT	30-	42	11		
g PSE	31-	43	31		Keys in program
X≷Y	32-		34		
g PSE	33-	43	31		
g GTO 29	34-43,	33	29	J	

Running Another Program


To run a program that does not begin with program line 01:

- 1. Press f P/R to set the calculator to Run mode. If the calculator is already in Run mode, skip this step.
- 2. Press ggto followed by two digits that specify the first line of the program.
- 3. Press R/S.

Example: Run the office-supplies program, now stored in the calculator beginning at program line 19, for the typewriter listing for \$625.

Keystrokes	Display	
f P/R	12,000.00	Sets calculator to Program mode.
g GTO 19	12,000.00	Sets calculator to first line of program to be executed.
625 _{R/S}	473.75	Net cost of typewriter.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 122 of 209



Page: 123 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Section 12

Real Estate and Lending

Annual Percentage Rate Calculations With Fees

Borrowers are usually charged fees in connection with the issuance of a mortgage, which effectively raises the interest rate. The actual amount received by the borrower (PV) is reduced, while the periodic payments remain the same. Given the life or term of the mortgage, the interest rate, the mortgage amount, and the basis of the fee charge (how the fee is calculated), the true Annual Percentage Rate (APR) may be calculated. Information is entered as follows:

- 1. Press 9 END and f CLEAR FIN.
- 2. Calculate and enter the periodic payment amount of the loan.
 - a. Key in the total number of payment periods; press n.
 - b. Key in the periodic interest rate (as a percentage); press i.
 - c. Key in the mortgage amount; press PV.*
 - d. To obtain the periodic payment amount, press PMT.*
- 3. Calculate and key in the actual net amount disbursed.*
 - If fees are stated as a percentage of the mortgage amount (points), recall
 the mortgage amount (RCL PV) key in the fee (percentage) rate; press
 % PV.
 - If fees are stated as a flat charge, recall the mortgage amount (RCL PV);
 key in the fee amount (flat charge); press PV.
 - If fees are stated as a percentage of the mortgage amount plus a flat charge, recall the mortgage amount (RCL PV); key in the fee (percentage) rate, press %—; key in the fee amount (flat charge); press
- 4. Press i to obtain the interest rate per compounding period.
- 5. To obtain the annual nominal percentage rate, key in the number of periods per year, then press X.

124

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 124 of 209

^{*} Positive for cash received; negative for cash paid out.

Example 1: A borrower is charged 2 points for the issuance of his mortgage. If the mortgage amount is \$60,000 for 30 years and the interest rate is $11^{1}/_{2}\%$ per year, with monthly payments, what true annual percentage rate is the borrower paying? (One point is equal to 1% of the mortgage amount.)

Keystrokes	Display	
g END		
f CLEAR FIN		
30 g 12x	360.00	Months (into n)
11.5g12÷	0.96	Percent monthly interest rate (into i).
60000 PV	60,000.00	Loan amount (into PV).
PMT	-594.17	Monthly payment (calculated).
RCL PV 2 % - PV	58,800.00	Actual amount received by borrower (into PV).
i	0.98	Percent monthly interest rate (calculated).
12×	11.76	Annual percentage rate.

Example 2: Using the same information as given in example 1, calculate the APR if the mortgage fee is \$150 instead of a percentage.

Keystrokes	Display	
g END		
f CLEAR FIN		
30 g 12x	360.00	Months (into n)
11.5 g 12÷	0.96	Percent monthly interest rate (into i).
60000 PV	60,000.00	Loan amount (into PV).
PMT	-594.17	Monthly payment (calculated).
RCL PV 150 - PV	59,850.00	Effective mortgage amount (into PV).
	0.00	
i	0.96	Monthly interest rate (calculated).
12×	11.53	Annual percentage rate.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 125 of 209

126 Section 12: Real Estate and Lending

Example 3: Again using the information given in example 1, what is the APR if the mortgage fee is stated as 2 points plus \$150?

Keystrokes	Display	
g END		
f CLEAR FIN		
30 g 12x	360.00	Months (into n)
11.5 g 12÷	0.96	Percent monthly interest rate (into i).
60000 PV	60,000.00	Loan amount (into PV).
PMT	-594.17	Monthly payment (calculated).
RCL PV 2 % -	58,800.00	
150-PV	58,650.00	Effective mortgage amount (into PV).
i	0.98	Monthly interest rate (calculated).
12×	11.80	Annual percentage rate.

Price of a Mortgage Traded at a Discount or Premium

Mortgages may be bought and/or sold at prices lower (discounted) or higher (at a premium) than the remaining balance of the loan at the time of purchase. Given the amount of the mortgage, the periodic payment, the timing and amount of the balloon or prepayment, and the *desired* yield rate, the price of the mortgage may be found. It should be noted that the balloon payment amount (if it exists) occurs coincident with, and does not include, the last periodic payment amount.

Information is entered as follows:

- 1. Press 9 END and f CLEAR FIN.
- 2. Key in the total number of periods until the balloon payment or prepayment occurs; press n. (If there is no balloon payment, key in total number of payments and press n.)
- 3. Key in the desired periodic interest rate (yield) and press i.
- 4. Key in the periodic payment amount; press PMT.*
- 5. Key in the balloon payment amount and press FV.* (If there is no balloon payment, go to step 6.)
- 6. Press PV to obtain the purchase price of the mortgage.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 126 of 209

^{*} Positive for cash received; negative for cash paid out.

Example 1: A lender wishes to induce the borrower to prepay a low interest rate loan. The interest rate is 5% with 72 payments remaining of \$137.17 and a balloon payment at the end of the sixth year of \$2000. If the lender is willing to discount the future payments at 9%, how much would the borrower need to prepay the note?

Keystrokes	Display	
g END f CLEAR FIN		
72 n	72.00	Months (into n).
9 g 12÷	0.75	Discount rate (into i).
137.17 PMT *	137.17	Monthly payments (into PMT).
2000 FV PV	-8,777.61	Amount necessary to prepay the note.

Example 2: A $9^1/_2\%$ mortgage with 26 years remaining and a remaining balance of \$49,350 is available for purchase. Determine the price to pay for this mortgage if the desired yield is 12%. (Since the payment amount is not given, it must be calculated.)

Keystrokes	Display	
9 END f CLEAR FIN		
26 g 12x	312.00	Months (into n).
9.5 g 12÷	0.79	Percent monthly interest rate (into i).
49350 CHS PV PMT	427.17	Monthly payment to be received (calculated).
12g12÷	1.00	Desired monthly interest rate (into i).
PV	-40,801.57	Purchase price to achieve the desired yield (calculated).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 127 of 209

^{*} Note that the payments are positive because this problem in seen from the viewpoint of the lender who will be receiving payments. The negative PV indicates money that was lent out.

Yield of a Mortgage Traded at a Discount or Premium

The annual yield of a mortgage bought at a discount or premium can be calculated given the original mortgage amount, interest rate, and periodic payment, as well as the number of payment periods per year, the price paid for the mortgage, and the balloon payment amount (if it exists).

Information is entered as follows:

- 1. Press 9 END and f CLEAR FIN.
- 2. Key in the total number of periods until the balloon payment occurs and press n. (If there is no balloon payment, key in the total number of periods and press n.)
- 3. Key in the periodic payment amount then press PMT.*
- 4. Key in the purchase price of the mortgage then press PV.*
- 5. Key in the balloon payment amount then press FV.* (If there is no balloon payment, go to step 6.)
- 6. Press i to obtain the yield per period.
- 7. Key in the number of periods per year and press X to obtain the nominal annual yield.

Example 1: An investor wishes to purchase a \$100,000 mortgage taken out at 9% for 21 years. Since the mortgage was issued, 42 monthly payments have been made. What would be the annual yield if the purchase price of the mortgage is \$79,000? (Since PMT was not given, it must be calculated).

Keystrokes	Display	
9 END f CLEAR FIN		
21 g 12x	252.00	Enter the number of periods (into n).
9 g 12÷	0.75	Monthly interest rate (into i).
100000 CHS PV	-100,000.00	Mortgage amount (into PV; negative to indicate money paid out).
PMT	884.58	Payment received (calculated).
RCL n	252.00	Recall number of periods.
42-n	210.00	Number of periods left after mortgage is bought (into n).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 128 of 209

^{*} Positive for cash received; negative for cash paid out.

Keystrokes	Display	
79000[HS][PV]	-79,000.00	Input price of mortgage (into PV; negative to indicate money paid out).
i	0.97	Yield per month (calculated).
12×	11.68	Percent annual yield.

Example 2: Using the same information given in example 1, calculate the annual yield if the loan is to be paid in full at the end of the fifth year (from original issuance). (In this case both the payment amount and the balloon must be calculated since they are not given.)

Keystrokes	Display	
9 END f CLEAR FIN 21 9 12x	252.00	Input the number of periods (into n).
9 g 12÷	0.75	Monthly interest rate (into PV).
100000 CHS PV	-100,000.00	Mortgage amount (into PV).
PMT	884.58	Payment (calculated).

Calculate the remaining balance of the loan after five years.

Calculate the remaining ba	lance of the loan o	itter tive years.
5 g 12x	60.00	Number of periods to be amortized.
FV	89,849.34	Remaining balance of the loan after five years.
RCL n	60.00	
42-n	18.00	New life of loan.
79000 CHS PV i	1.77	Percent monthly yield. (calculated).
12×	21.29	Percent annual yield.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 129 of 209

The Rent or Buy Decision

The question of whether to rent or purchase a residence is not always easy to answer, especially when the time period over which you would own or rent a house is short. This program performs an analysis which could be helpful in reaching a decision. Essentially, it calculates a yield or rate of return on the proposed investment. This yield may be compared with the yield obtained by renting a residence and investing the down payment and monthly payment differences in a savings account or other investment opportunity. This program takes into account the tax advantages obtained by a home owner on property taxes and mortgage interest.

First the program computes the Net Cash Proceeds upon Resale (*NCPR*),* next the yield on the investment in the house and then the value of the hypothetical savings account at the end of the investment period. A comparison of the *NCPR* and the final balance of the savings account and a comparison of the yields should aid in determining whether to rent or buy.

KEYSTROKES		DISPLAY		KEYSTROKES	Dis	SPLAY	
f P/R				FV	33-		15
f CLEAR PRGM	00-			R/S	34-		31
FV	01-		15	R↓	35-		33
FV+	02-		15	RCL n	36-	45	11
RCL7	03-	45	7	÷	37-		10
<u>%</u>	04-		25	RCL 4	38-	45	4
	05-		30	_	39-		30
RCL n	06-	45	11	RCL • 0	40-45	48	0
STO 0	07-	44	0	%	41-		25
RCL PV	08-	45	13	RCL PMT	42-	45	14
f CLEAR FIN	09-	42	34	RCL 4	43-	45	4

^{*} The Net Cash Proceeds upon Resale (*NCPR* = sales price – commission – mortgage balance), is the pre-tax proceeds. The program assumes that the buyer reinvests in like property and is not subject to capital gains tax.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 130 of 209

⁺ FV is repeated in the program twice to ensure that it is computed and not stored.

Section 12: Real Estate and Lending 131

	KEYSTROKES	DIS	PLAY	KEYSTROKES	DISPLAY	
1	RCL 1	10-	45	1 -	44-	301

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 131 of 209

Dimension: 14.8 cm x 21 cm

132 Section 12: Real Estate and Lending

REGISTERS						
n: Period	i: Apprec.	PV: Price	PMT: Used			
FV: Used	R _o : Period	R ₁ : Dwn Pmt	R ₂ : Life			
R ₃ : i(Mtg)	R ₄ : Taxes/Mo	R ₅ : Improve.	R ₆ : Closing C.			
R ₇ : % Comm.	R ₈ : Rent	R ₉ : Savings i	R _{.o} : Bracket			
R _{.1} : Unused.						

- 1. Key in the program.
- 2. Key in the estimated down payment then press STO 1.
- 3. Key in the life of the mortgage then press STO 2.
- 4. Key in the annual mortgage interest rate then press STO 3.
- 5. Key in the estimated monthly taxes then press STO 4.
- 6. Key in the total amount estimated for monthly repairs, improvements, incremental insurance, utility costs, and other expenses, then press STO 5.
- 7. Key in the closing costs then press STO 6.
- 8. Key in the selling cost as a percentage of the selling price. This should include sales commission, escrow fees, etc. then press [STO]7.
- 9. Key in the monthly rent for the alternative housing then press STO 8.
- 10. Key in the savings or alternative investment annual interest rate as a percentage then press STO 9.
- 11. Key in the combined State and Federal marginal tax rate* as a percentage then press STO 0.
- 12. Press f CLEAR FIN then key in the number of years involved in the investment; press n.
- 13. Key in the estimated rate of yearly appreciation as a percentage then press i.
- 14. Key in the price of the house under consideration then press PV.
- 15. Press R/S to compute the net proceeds from the sale of the house. (A negative value indicates money lost.)

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 132 of 209

^{*} The user should key in the total marginal income tax — Federal plus State — to obtain calculations which reflect the tax advantages of home ownership. Because of the complexities of tax laws and different financial and tax considerations for each individual, this program should only serve as a guide in considering an investment of this type. For more specific, detailed information, consult a tax accountant or qualified tax advisor.

- 16. Press R/S to compute the yield on your investment in the house.*
- 17. Press R/S to compute the value of a savings account or other investment.
- 18. Compare the value of the hypothetical savings account to the net proceeds of the sale of the house. Examine the sign and magnitude of the yield to arrive at your decision.
- 19.To change data and repeat the calculations, store the changed values in the appropriate registers and go to step 12.

Example: You are being transferred for 4 years to a distant city and are faced with the decision of whether to rent or to buy a house. A quick survey of the housing market indicates that you can purchase an acceptable house for \$70,000 with a \$7,000 down payment on a 30 year mortgage at 12% interest. The closing costs would be about \$1200. Selling costs include a 6% commission for resale and miscellaneous other fees that amount to another 2% of the sale price. Housing in the area is appreciating 10% per year. Property taxes would be about \$110 per month, and you estimate that maintenance would cost an additional \$65 per month.

An alternative would be to rent a similar dwelling at \$400 per month and to invest the difference between the purchase cost and rent at $6^1/_4\%$ interest. Your personal income tax rate (marginal) is 25% Federal and 5% State. Which alternative is more financially attractive?

Keystrokes	Display	
f CLEAR REG	0.00	
7000 STO 1	7,000.00	Down payment.
30STO 2	30.00	Life of mortgage.
12STO 3	12.00	Interest rate.
110STO4	110.00	Property taxes.
65ST05	65.00	Monthly expenses.
1200 <u>sto</u> 6	1,200.00	Closing costs.
8 <u>STO</u> 7	8.00	Resale costs (as a percentage).
400 STO 8	400.00	Rent.
6.25STO9	6.25	Savings interest rate.
30STO • 0	30.00	Tax bracket.
f CLEAR FIN	30.00	Clear financial registers.

^{*} If the calculator displays a negative result or **Error 5** when solving for yield then your investment has resulted in a loss. The amount of interest earned on the alternative investment is not taken into account in this calculation.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 133 of 209

134 Section 12: Real Estate and Lending

Keystrokes	Display	
4 <u>n</u>	4.00	Years in investment.
10 i	10.00	Yearly appreciation rate.
70000 PV	70,000.00	House price.
R/S	32,391.87	NCPR (calculated).
R/S	19.56	Yield.
R/S	21,533.79	Balance in savings.

By purchasing a house, you would gain \$10,858.08 (32,391.87 – 21,533.79) over an alternate investment at 6.25% interest.

Deferred Annuities

Sometimes transactions are established where payments do not begin for a specified number of periods; the payments are deferred. The technique for calculating *NPV* may be applied assuming zero for the first cash flow. Refer to pages 58 through 62.


Example 1: You have just inherited \$20,000 and wish to put some of it aside for your daughter's college education. You estimate that when she is of college age, 9 years from now, she will need \$7,000 at the beginning of each year for 4 years for college tuition and expenses. You wish to establish a fund which earns 6% annually. How much do you need to deposit in the fund today to meet your daughter's educational expenses?

Keystrokes	Display	
f CLEAR REG	0.00	Initialize.
O g CFo	0.00	First cash flow.
O g CFi 8 g Ni	0.00 8.00	Second through ninth cash flows.
7000 g CF _j 4 g N _j	7,000.00 4.00	Tenth through thirteenth cash flows.
6 i	6.00	Interest.
f NPV	15,218.35	NPV.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 134 of 209

Leases often call for periodic contractual adjustments of rental payments. For example, a 2-year lease calls for monthly payments (at the beginning of the month) of \$500 per month for the first 6 months, \$600 per month for the next 12 months, and \$750 per month for the last 6 months. This situation illustrates what is called a "step-up" lease. A "step-down" lease is similar, except that rental payments are decreased periodically according to the lease contract. Lease payments are made at the beginning of the period.

In the example cited, the rental payment stream for months 7 through 24 are "deferred annuities," as they start at some time in the future. The cash flow diagram from the investor's viewpoint looks like this:



To find today's present value of the cash flows assuming a desired yield, the *NPV* technique may be used. (Refer to pages 58 thru 62.)

Example 2: A 2-year lease calls for monthly payments (at the beginning of the month) of \$500 per month for the first 6 months, \$600 per month for the next 12 months, and \$750 per month for the last 6 months. If you wish to earn 13.5% annually on these cash flows, how much should you invest (what is the present value of the lease)?

Keystrokes	Display	
f CLEAR REG	0.00	Initialize.
500 g CFo	500.00	First cash flow.
g CF _j 5 g N _j	500.00 5.00	Second thru sixth cash flows.
600 g CF; 12 g N;	600.00 12.00	Next twelve cash flows.
750 g CF ₁ 6 g N ₁	750.00 6.00	Last six cash flows.
13.5 9 12÷	1.13	Monthly interest rate.
f NPV	12,831.75	Amount to invest to achieve a 13.5% yield.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 135 of 209

Section 13

Investment Analysis

Partial-Year Depreciation

For both income tax purposes and financial analyses, it is valuable to calculate depreciation based on a calendar or fiscal accounting year. When the acquisition date of an asset does not coincide with the start of the year — which is the rule rather than the exception — the amounts of depreciation in the first and last years are computed as fractions of a full year's depreciation.

Straight-Line Depreciation

The following hp 12c program calculates the straight-line depreciation for the year desired with the acquisition date occurring at any time during the year.

KEYSTROKES	DISPLAY		KEYSTROKES	DIS	PLAY	
f P/R			_	21-		30
f CLEAR PRGM	00-		n	22-		11
1	01-	1	RCL 0	23-	45	0
2	02-	2	g x=0	24-	43	35
÷	03-	10	9 БТО 35	25-43,	33	35
STO 1	04- 44	1	RCL 2	26-	45	2
X≶À	05-	34	g PSE	27-	43	31
STO 2	06- 44	2	RCL 0	28-	45	0
1	07-	1	f SL	29-	42	23
	08-	30	R/S	30-		31
STO 0	09- 44	0	1	31-		1
1	10-	1	STO +0	32-44	40	0
fSL	11- 42	23	STO + 2	33-44	40	2
RCL 1	12- 45	1	9 вто 26	34-43,	33	26
X	13-	20	RCL 2	35-	45	2

136

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 136 of 209

KEYSTROKES	DISPLAY		KEYSTROKES	DIS	DISPLAY		
STO 3	14-	44	3	g PSE	36-	43	31
RCL PV	15-	45	13	RCL PV	37-	45	13
X≷Y	16-		34	RCL FV	38-	45	15
_	17-		30	_	39-		30
PV	18-		13	RCL 3	40-	45	3
RCL n	19-	45	11	9 БТО 30	41-43,	33	30
RCL 1	20-	45	1	f P/R			

REGISTERS					
n: Life	i: Unused	PV: Dep. Value	PMT: Unused		
FV: Salvage	R _o : Used	R ₁ : #Mos./12	R ₂ : Counter		
R ₃ : 1 st Yr. Dep.	R ₄ -R _{.4} : Unused				


- 1. Key in the program.
- 2. Press f CLEAR FIN.
- 3. Key in the book value then press PV.
- 4. Key in the salvage value then press FV.
- 5. Key in the life in years (an integer) then press $\boxed{\mathbf{n}}$.
- 6. Key in the year desired then press ENTER.
- 7. Key in the number of months in the first year and press R/S.* The display will show the amount of depreciation for the desired year. If desired, press XZY to see the remaining depreciable value then press RCLIPV RCL3+XZY-RCLIFV- to find the total depreciation from the first year through the current year.
- 8. Press R/S for the amount of depreciation and remaining depreciable value for the next year. Repeat this step for the following years.
- 9. For a new case, press $\[\]$ GTO 00 and return to step 2.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 137 of 209

^{*} The display will pause showing the year number before showing the amount of depreciation for that year.

138 Section 13: Investment Analysis

Note: If the number of months in the first calendar year is less than 12, the amount of depreciation in the 1st year will be less than a full year's depreciation. The actual number of years that depreciation will occur is equal to the life +1. For example, a drill has a life of 3 years and is purchased 3 months before the year end. The following time diagram shows that depreciation will occur over 4 calendar years.



Example 1: A property has just been purchased for \$150,000. The purchase price is allocated between \$25,000 for land and \$125,000 for improvements (building). The remaining useful life of the building is agreed to be 25 years. There is no salvage value forecasted at the end of the useful life of the building. Thus, the depreciable value and book value is \$125,000.

The building was acquired 4 months before the end of the year. Using straight-line depreciation, find the amount of depreciation and remaining depreciable value for the 1st, 2nd, 25th, and 26th years. What is the total depreciation after 3 years?

Keystrokes	Display	
f CLEAR FIN		Salvage value = 0 so $FV = 0$.
125000 PV	125,000.00	Book value.
25 _n	25.00	Life.
1 ENTER	1.00	Year desired.
4R/S x > y	1.00 1,666.67 123,333.33	First year: depreciation, remaining depreciable value.
R/S XEY	2.00 5,000.00 118,333.33	Second year: depreciation, remaining depreciable value.
R/S	3.00 5,000.00	Third year: depreciation.
X&YRCL PV RCL 3 + X&Y - 9 GTO 00	11,666.67	Total depreciation through third year.
f CLEAR FIN	11,666.67	
125000 PV	125,000.00	Book value.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 138 of 209

Keystrokes	Display	
25 n	25.00	Life.
25 ENTER	25.00	Year desired.
4[R/S] [X \times Y]	25.00 5,000.00 3,333.33	Twenty-fifth year: depreciation, remaining depreciable value.
R/S x≥y	26.00 3,333.33 0.00	Twenty-sixth year: depreciation, remaining depreciable value.

Example 2: A new car was purchased for 6,730 with $4^{1}/_{2}$ months remaining in the year. If the expected life of the car is 5 years, what is the amount of depreciation in the first year?

Keystrokes	Display	
g GTO 00 f CLEAR FIN		
6730 PV	6,730.00	Book value.
5 n	5.00	Life.
1 ENTER	1.00	
4.5 _{R/S}	1.00 504.75	First year: depreciation.

Declining-Balance Depreciation

The following hp 12c program calculates the declining-balance depreciation for the year desired with the acquisition date occurring at any time during the year.

KEYSTROKES	DISPLAY		KEYSTROKES	DISPLAY			
f P/R				RCL 0	19-	45	0
f CLEAR PRGM	00-			g x=0	20-	43	35
1	01-		1	9 дто 31	21-43,	33	31
2	02-		2	RCL 2	22-	45	2
÷	03-		10	g PSE	23-	43	31
STO 1	04-	44	1	RCL 0	24-	45	0
X≷Y	05-		34	f DB	25-	42	25
STO 2	06-	44	2	R/S	26-		31

Page: 139 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

140 Section 13: Investment Analysis

KEYSTROKES	DISPLAY			KEYSTROKES	DISPLAY		
1	07-		1	1	27-		1
	08-		30	STO+0	28-44	40	0
STO 0	09-	44	0	STO +2	29-44	40	2
1	10-		1	9 GTO 22	30-43,	33	22
f DB	11-	42	25	RCL 2	31-	45	2
RCL 1	12-	45	1	g PSE	32-	43	31
X	13-		20	RCL PV	33-	45	13
STO3	14-	44	3	RCL FV	34-	45	15
RCL PV	15-	45	13	_	35-		30
X≷Y	16-		34	RCL 3	36-	45	3
_	17-		30	9 GTO 26	37-43,	33	26
PV	18-		13	f P/R			

REGISTERS					
n: Life	i: Factor	PV: Dep. Value	PMT: Unused		
FV: Salvage	R _o : Used	R ₁ : #Mos./12	R ₂ : Counter		
R ₃ :1 st Yr. Dep.	R ₄ –R _{.4} : Unused				

- 1. Key in the program.
- 2. Press f CLEAR FIN.
- 3. Key in the book value then press PV.
- 4. Key in the salvage value then press FV.
- 5. Key in the declining-balance factor as a percentage then press i.
- 6. Key in the life in years (an integer) then press n.
- 7. Key in the year desired then press ENTER.
- 8. Key in the number of months in first year* and press R/S.† The display will show the amount of depreciation for the desired year. Press X to see the

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 140 of 209

^{*} Refer to straight-line depreciation instruction note, page 137.

[†] The display will pause showing the year number before showing the amount of depreciation for that year.

- Press R/S for the amount of depreciation then, if desired, press X Y for the remaining depreciable value for the next year. Repeat this step for the following years.
- 10. For a new case press $\cent{9GTO}$ 00 and return to step 2.

Example: An electron beam welder which costs \$50,000 is purchased 4 months before the end of the accounting year. What will the depreciation be during the first full accounting year (year 2) if the welder has a 6 year depreciable life, a salvage value of \$8,000 and is depreciated using the declining-balance depreciation method? The declining-balance factor is 150%.

Keystrokes	Display	
f CLEAR FIN		
50000 PV	50,000.00	Book value.
8000 FV	8,000.00	Salvage value.
150 i	150.00	Declining-balance factor.
6 n	6.00	Life.
2 ENTER	2.00	Year desired.
4R/S	2.00 11,458.33	Second year: depreciation.

Sum-of-the-Years-Digits Depreciation

The following hp 12c program calculates the sum-of-the-years-digits depreciation for the year desired with the acquisition date occurring at any time during the year.

KEYSTROKES	DISPLAY	KEYSTROKES	DISPLAY
f P/R			21- 30
f CLEAR PRGM	00-	n	22- 11
1	01- 1	RCL 0	23- 45 0
2	02- 2	g x=0	24- 43 35
÷	03- 10	9 сто 35	25-43, 33 35
STO 1	04- 44 1	RCL 2	26- 45 2
x ≷ y	05- 34	g PSE	27- 43 31

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 141 of 209

142 Section 13: Investment Analysis

KEYSTROKES	DISPLAY			KEYSTROKES	DISPLAY		
STO 2	06-	44	2	RCL 0	28-	45	0
1	07-		1	f SOYD	29-	42	24
_	08-		30	R/S	30-		31
STO 0	09-	44	0	1	31-		1
1	10-		1	STO+0	32-44	40	0
f SOYD	11-	42	24	STO +2	33-44	40	2
RCL 1	12-	45	1	9 GTO 26	34-43,	33	26
X	13-		20	RCL 2	35-	45	2
вто 3	14-	44	3	g PSE	36-	43	31
RCL PV	15-	45	13	RCL PV	37-	45	13
X≷Y	16-		34	RCLFV	38-	45	15
_	17-		30	_	39-		30
PV	18-		13	RCL 3	40-	45	3
RCL n	19-	45	11	9 GTO 30	41-43,	33	30
RCL 1	20-	45	1	f P/R			

REGISTERS						
n: Life	i: Unused	PV: Dep. Value	PMT: Unused			
FV: Salvage	R _o : Used	R ₁ : #Mos./12	R ₂ : Counter			
R ₃ : 1 st Yr. Dep. R ₄ -R _{.4} : Unused						

- 1. Key in the program.
- 2. Press f CLEAR FIN.
- 3. Key in the book value then press PV.
- 4. Key in the salvage value then press FV.
- 5. Key in the life in years (an integer) then press <a>n.
- 6. Key in the year desired then press ENTER.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 142 of 209

- 7. Key in the number of months in first year* then press R/S.† The display will show the amount of depreciation for the desired year. If desired, press x to see the remaining depreciable value, then press RCL PV RCL 3 + X Y RCL FV to find the total depreciation through the current year.
- 8. Press R/S for the amount of depreciation then, if desired, press X for the remaining depreciable value for the next year. Repeat this step for the following years.
- 9. For a new case press 9 GTO 00 and return to step 2.

Example: A commercial movie camera is purchased for \$12,000. If maintained properly, the camera has a useful life expectancy of 25 years with \$500 salvage value. Using the sum-of-the-years-digits method, what is the amount of depreciation and the remaining depreciable value for the 4th and 5th years? Assume the first depreciation year is 11 months long.

Keystrokes	Display	
f CLEAR FIN		
12000 PV	12,000.00	Book value.
500 FV	500.00	Salvage value.
25 _n	25.00	Life.
4 ENTER	4.00	Year desired.
11 <u>R/S</u> [xey]	4.00 781.41 8,238.71	Fourth year: depreciation, remaining depreciable value.
R/S x e y	5.00 746.02 7,492.69	Fifth year: depreciation, remaining depreciable value.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 143 of 209

^{*} Refer to straight-line depreciation instruction note, page 137.

[†] The display will pause showing the year number before showing the amount of depreciation for that year.

Full- and Partial-Year Depreciation with Crossover

When calculating declining-balance depreciation it is often advantageous for tax purposes to switch from declining balance to straight-line depreciation at some point. This hp 12c program calculates the optimum crossover point and automatically switches to straight-line depreciation at the appropriate time. The crossover point is the end of the year in which the declining-balance depreciation last exceeds or equals the amount of straight-line depreciation. The straight-line depreciation is determined by dividing the remaining depreciable value by the remaining useful life.

Given the desired year and the number of months in the first year, this program calculates the depreciation for the desired year, the remaining depreciable value, and the total depreciation through the current year.

KEYSTROKES	DI	SPLAY		KEYSTROKES	DIS	PLAY	
f P/R				RCL 4	48-	45	4
f CLEAR PRGM	00-			÷	49-		10
1	01-		1	g x≤y	50-	43	34
2	02-		2	9 вто 53	51-43,	33	53
÷	03-		10	9 GTO 65	52-43,	33	65
STO 6	04-	44	6	R↓	53-		33
RCL n	05-	45	11	0	54-		0
X≷Y	06-		34	RCL 0	55-	45	0
	07-		30	g x≤y	56-	43	34
STO 4	08-	44	4	9 вто 86	57-43,	33	86
R↓	09-		33	RCL PV	58-	45	13
STO 0	10-	44	0	RCL 5	59-	45	5
1	11-		1	_	60-		30
STO-0	12-44	30	0	PV	61-		13
STO 2	13-	44	2	1	62-		1
STO 3	14-	44	3	STO -4	63-44	30	4
f DB	15-	42	25	9 GTO 40	64-43,	33	40
RCL 6	16-	45	6	RCL 4	65-	45	4

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 144 of 209

KEYSTROKES	DI	SPLAY		KEYSTROKES	DIS	PLAY	
X	17-		20	n	66-		11
STO 1	18-	44	1	0	67-		0
RCL PV	19-	45	13	STO 6	68-	44	6
X ≷ Y	20-		34	1	69-		1
=	21-		30	STO -2	70-44	30	2
PV	22-		13	STO+0	71-44	40	0
ENTER	23-		36	RCL 5	72-	45	5
g LSTx	24-	43	36	STO - 1	73-44	30	1
X ≷ Y	25-		34	RCL 3	74-	45	3
RCLFV	26-	45	15	fSL	75-	42	23
_	27-		30	STO +1	76-44	40	1
X≶Ŋ	28-		34	1	77-		1
RCL O	29-	45	0	STO - O	78-44	30	0
1	30-		1	STO +2	79-44	40	2
g x≤y	31-	43	34	STO +3	80-44	40	3
9 GTO 39	32-43,	33	39	R↓	81-		33
R↓	33-		33	RCL 0	82-	45	0
R↓	34-		33	1	83-		1
1	35-		1	g x≼y	84-	43	34
g PSE	36-	43	31	9 GTO 74	85-43,	33	74
R↓	37-		33	R↓	86-		33
R/S	38-		31	R↓	87-		33
1	39-		1	RCL 2	88-	45	2
STO +2	40-44	40	2	g PSE	89-	43	31
STO - O	41-44	30	0	R↓	90-		33
f DB	42-	42	25	R/S	91-		31

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 145 of 209

Dimension: 14.8 cm x 21 cm

146 Section 13: Investment Analysis

KEYSTROKES	DI	SPLAY	•	KEYSTROKES	DIS	PLAY	
STO +1	43-44	40	1	RCL 6	92-	45	6
STO 5	44-	44	5	g x=0	93-	43	35
RCL PV	45-	45	13	9 GTO 74	94-43,	33	74
RCLFV	46-	45	15	9 сто 58	95-43,	33	58
_	47-		30	f P/R			

REGISTERS					
n: Life	i: Factor	PV: Dep. Value	PMT: Unused		
FV: Salvage	R _o : Used	R ₁ : Dep.	R ₂ : Counter		
R ₃ : Used	R _{4:} Used	R _{5:} Used	R _{6:} Used		

- 1. Key in the program.
- 2. Press f CLEAR REG.
- 3. Key in the book value then press PV.
- 4. Key in the salvage value then press FV.
- 5. Key in the life in years (an integer) then press n.
- 6. Key in the declining-balance factor as a percentage then press i.
- 7. Key in the desired year and press ENTER.
- 8. Key in the number of months in the first year* then press R/S † to calculate the amount of depreciation for the desired year.
- 9. If desired, press [XEY] to see the remaining depreciable value.
- 10. If desired, press RCL 1 to see the total depreciation through the current year.
- 11. Continue pressing \mathbb{R}/\mathbb{S} * to find the amount of depreciation for the successive years. Steps 9 and 10 may be repeated for each year.
- 12. For a new case press 9 GTO 00 and return to step 2.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 146 of 209

^{*} Refer to straight-line depreciation note page 137.

[†] The display will pause with the year number before displaying the amount of depreciation for that year.

Example: An electronic instrument is purchased for \$11,000, with 6 months remaining in the current fiscal year. The instrument's useful life is 8 years and the salvage value is expected to be \$500. Using a 200% declining-balance factor, generate a depreciation schedule for the instrument's complete life. What is the remaining depreciable value after the first year? What is the total depreciation after the 7th year?

Keystrokes	Display	
f CLEAR REG	0.00	
11000 PV	11,000.00	Book value.
500 FV	500.00	Salvage value.
8 n	8.00	Life.
200 i	200.00	Declining-balance factor.
1 ENTER	1.00	First year depreciation desired.
6\(\begin{align*} \(\mathbb{R} / \mathbb{S} \) \(\mathbb{X} \times \mathbb{Y} \) \(\mathbb{M} \times \mathbb{M} \)	1.00 1,375.00 9,125.00	First year: depreciation, remaining depreciable value.
R/S	2.00 2,406.25	Second year: depreciation.
R/S	3.00 1,804.69	Third year: depreciation.
R/S	4.00 1,353.51	Fourth year: depreciation.
R/S	5.00 1,015.14	Fifth year: depreciation.
R/S	6.00 761.35	Sixth year: depreciation.*
R/S	7.00 713.62	Seventh year: depreciation.
RCL 1	9,429.56	Total depreciation through the seventh year.
R/S	8.00 713.63	Eight year: depreciation
R/S	9.00 356.81	Ninth year: depreciation.

st By observation the crossover was year 6. Years 7, 8, and 9 use straight-line depreciation.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 147 of 209

Excess Depreciation

When accelerated depreciation is used, the difference between total depreciation charged over a given period of time and the total amount that would have been charged under straight-line depreciation is called excess depreciation. To obtain excess depreciation:

- 1. Calculate the total depreciation then press ENTER.
- 2. Key in the depreciable amount (cost less salvage) then press will. Key in the useful life of the asset in years then press :. Key in the number of years in the income projection period then press x to get the total straight-line depreciation charge.
- 3. Press _ to get the excess depreciation.

Example: What is the excess depreciation in the previous example over 7 calendar years? (Because of the partial first year, there are $6^1/_2$ years depreciation in the first 7 calendar years.)

Keystrokes	Display	
9429.56 ENTER	9,429.56	Total depreciation through seventh year.
10500 ENTER	10,500.00	Depreciable amount.
8 ÷	1,312.50	Yearly straight-line depreciation.
6.5×	8,531.25	Total straight-line depreciation.
_	898.31	Excess depreciation

Modified Internal Rate of Return

The traditional Internal Rate of Return (*IRR*) technique has several drawbacks which hamper its usefulness in some investment applications. The technique implicitly assumes that all cash flows are either reinvested or discounted at the computed yield rate. This assumption is financially reasonable as long as the rate is within a realistic borrowing and lending range (for example, 10% to 20%). When the *IRR* becomes significantly greater or smaller, the assumption becomes less valid and the resulting value less sound as an investment measure.

IRR also is limited by the number of times the sign of the cash flow changes (positive to negative or vice versa). For every change of sign, the *IRR* solution has the potential for an additional answer. The cash flow sequence in the example that follows has three sign changes and hence up to three potential internal rates of return. This particular example has three positive real answers: 1.86, 14.35, and 29. Although mathematically sound, multiple answers probably are meaningless as an investment measure.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 148 of 209

This Modified Internal Rate of Return procedure (MIRR) is one of several IRR alternatives which avoids the drawbacks of the traditional IRR technique. The procedure eliminates the sign change problem and the reinvestment (or discounting) assumption by utilizing user stipulated reinvestment and borrowing rates.

Negative cash flows are discounted at a safe rate that reflects the return on an investment in a liquid account. The figure generally used is a short-term security (T-Bill) or bank passbook rate.

Positive cash flows are reinvested at a reinvestment rate which reflects the return on an investment of comparable risk. An average return rate on recent market investments might be used.

The steps in the procedure are:

- Calculate the future value of the positive cash flows (NFV) at the reinvestment rate.
- 2. Calculate the present value of the negative cash flows (NPV) at the safe rate.
- 3. Knowing *n*, *PV*, and *FV*, solve for *i*.

Example: An investor has the following unconventional investment opportunity. The cash flows are:

Group	# of Months	Cash Flow (\$)
0	1	-180,000
1	5	100,000
2	5	-100,000
3	9	0
4	1	200,000

Calculate the MIRR using a safe rate of 6% and a reinvestment (risk) rate of 10%.

Keystrokes	Display	
f CLEAR REG	0.00	
OGCFO	0.00	First cash flow.
100000 g CFi		
5 g Ni	5.00	Second through sixth cash flows.
$0gCF_{i}5gN_{i}$	5.00	Next five cash flows.
$0gCF_{i}9gN_{i}$	9.00	Next nine cash flows.
200000 g CFi	200,000.00	Last cash flow.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 149 of 209

150 Section 13: Investment Analysis

Keystrokes	Display	
10 g 12: f NPV	657,152.37	NPV of positive cash flows.
CHS PV		
20 n FV	775,797.83	NFV of positive cash flows.
180000 CHS 9 CFo		
$0gCF_{i}5gN_{i}$		
100000 CHS CFi		
$5gN_i$		
6 9 12÷ f NPV	-660,454.55	NPV of negative cash flows.
20 n i	0.81	Monthly MIRR
12×	9.70	Annual MIRR.

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Page: 150 of 209

Dimension: 14.8 cm x 21 cm

Section 14

Leasing

Advance Payments

Situations may exist where payments are made in advance (leasing is a good example). These agreements call for extra payments to be made when the transaction is closed.

This first procedure finds the periodic payment amount necessary to achieve a desired yield when a number of payments are made in advance. And, given the periodic payment, the second procedure calculates the periodic yield.

Solving For Payment

To calculate the payment, information is entered as follows:

- 1. Press 9 END and f CLEAR FIN.
- 2. Key in the total number of payments in the lease then press ENTER.
- 3. Key in the total number of payments made in advance then press STO|0-\(\bar{n}\).
- 4. Key in or calculate the periodic interest rate as a percentage then press i.
- 5. Press 1 CHS PV RCL 0 +.
- 6. Key in the initial loan amount then press (**) +, to obtain the periodic payment to be received by the lessor.

Example 1: Equipment worth \$750 is leased for 12 months. The equipment is assumed to have no salvage value at the end of the lease. The lessee has agreed to make three payments at the time of closing. What monthly payment is necessary to yield the lessor 10% annually?

Keystrokes	Display	
g END		
f CLEAR FIN		
12 ENTER	12.00	Duration of lease.
3STO 0 - n	9.00	Number of periodic payments.
10g12÷	0.83	
1 CHS PMT	-1.00	
PV RCL 0 +	11.64	
750×≥y ÷	64.45	Monthly payment to be received.

151

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 151 of 209

152 Section 14: Leasing

If solving for the payment amount will be done repetitively, key in the following hp 12c program.

KEYSTROKES	I	DISPLAY	•	KEYSTROKES	D	ISPLAY	
f P/R				1	09-		1
f CLEAR PRGM	00-			CHS	10-		16
g END	01-	43	8	PMT	11-		14
f CLEAR FIN	02-	42	34	PV	12-		13
RCL 0	03-	45	0	RCL 1	13-	45	1
RCL 1	04-	45	1	+	14-		40
_	05-		30	RCL 3	15-	45	3
n	06-		11	X≶Y	16-		34
RCL 2	07-	45	2	÷	17-		10
i	08-		12	f P/R			

REGISTERS						
n: n-#Adv. Pmt.	i: i	PV: Used	PMT: -1			
FV: 0	R _o : n	R ₁ : #Adv. Pmt.	R ₂ : i			
R ₃ : Loan	R ₄ –R _{.7} : Unused					

- 1. Key in the program.
- 2. Key in the total number of payments in the lease then press STO 0.
- 3. Key in the total number of payments made in advance then press STO 1.
- 4. Key in the periodic interest rate as a percentage then press STO2.
- 5. Key in the loan amount and press $\overline{\text{STO}}3$; then press $\overline{\text{R/S}}$ to obtain the periodic payment to be received by the lessor.
- 6. For a new case, return to step 2. The values changed from the previous case are the only values which need to be entered.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 152 of 209

Example 2: Using the preceding program, solve for the monthly payment using the information given in example 1. Then change the yearly interest to 15% and solve for the new payment amount.

Keystrokes	Display	
12STO0	12.00	Duration of lease.
3 <u>STO</u> 1	3.00	Number of advance payments.
10 ENTER 12 ÷		
STO 2	0.83	Periodic interest rate.
750STO3R/S	64.45	Monthly payment to be received.
15 ENTER 12 ÷		
STO 2 R/S	65.43	Monthly payment to achieve a 15% yield.

Example 3: Using the information from example 1, what monthly payment is necessary to yield the lessor 15% annually if one payment is due at the time of closing?

Assuming that the previous example was just solved, the keystrokes are as follows:

Keystrokes	Display	
1STO 1R/S	66.86	Monthly payment to be received.

Since this problem is an annuity due situation (one payment at the beginning of the period) the calculation could also be done as follows:

Keystrokes	Display	
9 BEG		
f CLEAR FIN		
12n15g12÷	1.25	Periodic interest rate (into i).
750 CHS PV PMT	66.86	Monthly payment to be received.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 153 of 209

154 Section 14: Leasing

Solving for Yield

To calculate the periodic yield, information is entered as follows:

- 1. Press 9 END and f CLEAR FIN.
- 2. Key in the total number of payments in the lease then press ENTER.
- 3. Key in the total number of payments made in advance then press STOO-n.
- 4. Key in the periodic payment to be received then press PMT.
- 5. Key in the total amount of the loan then press CHS_RCL_ORCL_PMT_X + PV.
- 6. Press i to obtain the periodic yield.

Example 1: A lease has been written to run for 60 months. The leased equipment has a value of \$25,000 with a \$600 monthly payment. The lessee has agreed to make 3 payments at the time of closing (\$1800). What is the annual yield to the lessor?

Keystrokes	Display	
g END		
f CLEAR FIN		
60ENTER 3		
STO O - n	57.00	Number of periodic payments.
600 PMT		
25000 CHS RCL 0	3.00	Number of advance payments.
$\boxed{RCL}\boxed{PMT}\boxed{X}\boxed{+}\boxed{PV}$	-23,200.00	PV.
i	1.44	Monthly yield (calculated).
12×	17.33	Annual yield (as a percentage).

	г 1		Г		• • • • • • • • • • • • • • • • • • • •			1111			· .I					1 (
- 1		Wina 1	or.	งกอเส	14/111	ho r	iono re	petitive	\/ I	/O\/	in th	na t	\sim 1	lowing	hn	. ,,	nroar	am.
- 1	30	villa i	OI.	VICIU	77 111	טב נ	aone re		v , 1	\sim	111 11	10 1	OI.	iowilla i	IIV.	1 4	. DIOGI	uiii.

KEYSTROKES		DISPLAY		KEYSTROKES	DISPLAY	
f P/R				RCL 3	09- 45	3
f CLEAR PRGM	00-			CHS	10-	16
g END	01-	43	8	RCL 1	11- 45	1
f CLEAR FIN	02-	42	34	RCL PMT	12- 45	14
RCL 0	03-	45	0	X	13-	20
RCL 1	04-	45	1	+	14-	40
_	05-		30	PV	15-	13
n	06-		11	i	16-	12
RCL 2	07-	45	2	RCL g 12÷	17-45, 43	12
PMT	08-		14	f P/R		

REGISTERS				
n: n-#Adv. Pmts.	i: i	PV: Used	PMT: Pmt.	
FV: 0	R _o : n	R ₁ : Adv. Pmts.	R ₂ : Pmt.	
R ₃ : Loan	$R_4 - R_7$: Unused			

- 1. Key in the program.
- 2. Key in the total number of payments in the lease then press STO 0.
- 3. Key in the total number of payments made in advance then press STO 1.
- 4. Key in the periodic payment to be received then press $\overline{\mbox{\scriptsize STO}}\mbox{\scriptsize 2}.$
- 5. Key in the total amount of the loan, then press $\overline{STO}3$; then press $\overline{R/S}$ to obtain the periodic yield.
- 6. For a new case, return to step 2. The values changed from the previous case are the only values which need to be re-entered.

Example 2: Using the program, solve for yield using the same information given in example 1. Then change the payment to \$625 and solve for the yield.

Keystrokes	Display	
60 <u>sto</u> 0	60.00	Number of payments.
3STO 1	3.00	Number of advance payments.
600[STO]2	600.00	Periodic payment.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 155 of 209

156 Section 14: Leasing

Keystrokes	Display	
25000STO3R/S	17.33	Annual yield (as a percentage).
625[STO]2[R/S]	19.48	Annual yield (as a percentage) when <i>PMT</i> is increased \$25.

Advance Payments With Residual

Situations may arise where a transaction has advance payments and a residual value (salvage value) at the end of the normal term.

Solving for Payment

The following program solves for the periodic payment amount necessary to achieve a desired yield.

KEYSTROKES		DISPLAY	•	KEYSTROKES	D	ISPLAY	
f P/R				FV	14-		15
f CLEAR PRGM	00-			RCL n	15-	45	11
g END	01-	43	8	RCL 4	16-	45	4
f CLEAR FIN	02-	42	34		17-		30
RCL 0	03-	45	0	n	18-		11
n	04-		11	1	19-		1
RCL 1	05-	45	1	CHS	20-		16
i	06-		12	PMT	21-		14
RCL 3	07-	45	3	PV	22-		13
FV	08-		15	RCL 4	23-	45	4
PV	09-		13	+	24-		40
RCL 2	10-	45	2	RCL 5	25-	45	5
+	11-		40	X≷Y	26-		34
STO 5	12-	44	5	÷	27-		10
0	13-		0	f P/R			

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 156 of 209

REGISTERS				
n: Used.	i: Interest	PV: Used	PMT: -1.	
FV: Residual	R _o : # Pmts (n)	R ₁ : Interest.	R ₂ : Loan.	
R ₃ : Residual	R₄: # Adv. Pmt.	R ₅ : Used	R ₆ –R _{.6} : Unused	

- 1. Key in the program.
- 2. Key in the total number of payments then press STO 0.
- 3. Key in or calculate the periodic interest rate then press STO 1.
- 4. Key in the loan amount then press STO 2.
- 5. Key in the residual value then press STO 3.
- 6. Key in the total number of payments made in advance then press $\boxed{\text{STO}}4$. Then press $\boxed{\text{R/S}}$ to obtain the payment amount received by the lessor.
- 7. For a new case, return to step 2. The values changed from the previous case are the only values which need to be re-entered.

Example 1: A copier worth \$22,000 is to be leased for 48 months. The lessee has agreed to make 4 payments in advance, with a purchase option at the end of 48 months enabling him to buy the copier for 30% of the purchase price. What monthly payment is necessary to yield the lessor 15% annually:



Keystrokes	Display	
48STO 0		
15 ENTER		
12 ÷ STO 1	1.25	Monthly interest rate.
22000 STO 2		
30 <u>%sto</u> 3		
4STO4R/S	487.29	Monthly payment received by lessor.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 157 of 209

158 Section 14: Leasing

Example 2: Using the information from example 1, what would the monthly payments be if the lessor desired a yield of 18% annually?

Keystrokes	Display	
	487.29	From previous example.
18ENTER 12 ÷	1.50	Monthly interest rate.
STO 1 R/S	520.81	Monthly payment received by lessor.


Solving For Yield

f CLEARREG
5000 CHS ENTER
145 ENTER 2

Solving for yield is essentially the same as solving for Internal Rate of Return (*IRR*). The keystrokes are as follows:

- 1. Press f CLEARREG.
- 2. Key in the amount of the first cash flow then press 9 CFo. This initial amount is the difference between the initial loan amount and any payments received at closing time. Observe the sign convention: positive for cash received and negative for cash paid out.
- 3. Key in the amount of the first cash flow then press <code>9 CFj</code>. Then key in the number of times that cash flow occurs then press <code>9 Nj</code>.
- 4. Key in $0\,$ \mathbb{G} \mathbb{G} then the number of advance payments minus one. Then press $\mathbb{G}[\mathbb{N}]$.
- 5. Key in the residual then press <code>GCFi</code>. Then press <code>fIRR</code> to solve for periodic yield.

Example: Equipment worth \$5000 is leased for 36 months at \$145 per month. The lessee has agreed to pay the first and last month's payments in advance. At the end of the lease, the equipment may be purchased for \$1500. What is the annual yield to the lessor if the equipment is purchased?



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 158 of 209

Section 14: Leasing 159

Keystrokes	Display	
X + g CFo	-4,710.00	Net amount of cash advanced.
145 g CFi 34 g Ni	34.00	Thirty-four cash flows of \$145.00.
O g CF _j	0.00	Thirty-fifth cash flow.
1500 g CFj	1,500.00	Thirty-sixth cash flow.
f IRR 12 X	18.10	Annual yield to lessor.

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Page: 159 of 209

Dimension: 14.8 cm x 21 cm

Section 15

Savings

Nominal Rate Converted to Effective Rate

Given a nominal interest rate and the number of compounding periods per year, this keystroke procedure computes the effective annual interest rate.

- 1. Press 9 END and f CLEAR FIN.
- 2. Key in the annual nominal rate as a percentage, then press ENTER.
- 3. Key in the number of compounding periods per year, then press $n \div i$.
- 4. Key in 100 then press CHS ENTER PV.
- 5. Press FV + to obtain the effective annual interest rate.

Example 1: What is the effective annual interest rate if the annual nominal rate of $5^{1}/_{4}\%$ is compounded quarterly?

Keystrokes	Display	
g END		
f CLEAR FIN		
5.25 ENTER	5.25	Nominal rate.
4n ÷ i	1.31	Percent quarterly interest rate.
100 CHS ENTER		
PV FV +	5.35	Percent effective interest rate.

For repeated calculations, the following hp 12c program can be used:

KEYSTROKES	DISPLAY		KEYSTROKES	DISPLA	Y	
f P/R				0	07-	0
f CLEAR PRGM	00-			0	08-	0
g END	01-	43	8	CHS	09-	16
f CLEAR FIN	02-	42	34	ENTER	10-	36
n	03-		11	PV	11-	13
÷	04-		10	FV	12-	15
i	05-		12	+	13-	40
1	06-		1	f P/R		

160

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 160 of 209

REGISTERS						
n: # Periods.	i: Nom. Rate/n	PV: 0	PMT: Used.			
FV: Eff. Rate	R _o –R _{.9} : Unused					

- 1. Key in the program.
- 3. Key in the number of compounding periods per year then press $\overline{\text{R/S}}$ to obtain the effective annual interest rate.
- 4. For a new case return to step 2.

Example 2:

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 161 of 209

162 Section 15: Savings

Nominal Rate Converted to Continuous Effective Rate

This procedure converts a nominal annual interest rate to the continuous effective rate.

- 1. Press 1 ENTER.
- 2. Key in the nominal rate as a percentage then press %.
- 3. Press $ge^x \Delta\%$.

Example: What is the effective rate resulting from a $5^1/_4\%$ passbook rate with continuous compounding?

Keystrokes	Display	
1 ENTER 5.25 %		
ge^x	1.05	
Δ%	5.39	Continuous rate.

Section 16

Bonds

30/360 Day Basis Bonds

A bond is a contract to pay interest, usually semiannually, at a given rate (coupon) and to pay the principal of the bond at some specified future date. A bond which is calculated on a 30/360 day basis is one in which the day count basis is computed using 30 days in a month and 360 days in a year.

The following program solves for the price given the yield or for the yield given the price of a semiannual coupon bond which is calculated on a 30/360 day basis and is held for more than six months.

KEYSTROKES	DISPLAY			KEYSTROKES	DISP	PLAY
f P/R				RCL 6	24-	4 5 6
f CLEAR PRGM	00-			X	25-	20
f CLEAR FIN	01-	42	34	RCL 0	26-	4 5 0
g BEG	02-	43	7	g x=0	27-	43 35
RCL 2	03-	45	2	9 сто 39	28-43,	33 39
2	04-		2	2	29-	2
÷	05-		10	÷	30-	10
PMT	06-		14	i	31-	12
STO 6	07-	44	6	PV	32-	13
RCL 5	08-	45	5	CHS	33-	16
+	09-		40	X≷Y	34-	34
FV	10-		15		35-	30
RCL 3	11-	45	3	g LSTx	36-	43 36
RCL 4	12-	45	4	X≷Y	37-	34
g adys	13-	43	26	9 GTO 00	38-43,	33 00

163

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 163 of 209

164 Section 16: Bonds

KEYSTROKES	ı	DISPLAY		KEYSTROKES	D	OISPLAY	
R↓	14-		33	R↓	39-		33
1	15-		1	RCL 1	40-	45	1
8	16-		8	+	41-		40
0	17-		0	CHS	42-		16
÷	18-		10	PV	43-		13
n	19-		11	i	44-		12
g FRAC	20-	43	24	2	45-		2
1	21-		1	X	46-		20
X≥y	22-		34	f P/R			
=	23-		30				

REGISTERS						
n: ∆ days/180	i: Yield/2	PV: Price	PMT: Coupon/2.			
FV: Red+Cpn./2	R _o : Yield	R ₁ : Price.	R ₂ : Coupon			
R ₃ : D _{set}	R ₄ : D _{mat}	R ₅ : Redemption	R ₆ : Coupon/2.			
R ₇ –R _{.3} : Unused						

- 1. Key in the program.
- 2. If the **C** status indicator is not displayed, press STO EEX.
- 3. Key in the annual coupon interest rate as a percentage then press STO 2.
- 4. Key in the settlement date (MM.DDYYYY)* then press STO 3.
- 5. Key in the maturity date (MM.DDYYYY)* then press STO 4.
- 6. Key in the redemption value as a percentage of par then press \$TO|5.
- 7. If price is desired:
 - a. Key in the desired yield to maturity as a percentage then press STO 0.
 - b. Press R/S to calculate price as a percentage of par value.
 - c. Press $\times Y$ to display accrued interest due the seller.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 164 of 209

^{*} For information about date format see pages 29 to 30.

165

For a new case return to step 3. Note that only those values which have been changed need to be reentered and stored.

- 8. If yield is desired:
 - a. Press OSTO 0.
 - b. Key in the price as a percentage of par value and press STO 1.
 - c. Press R/S to compute annual yield to maturity.

For a new case return to step 3. Note that only those values which have been changed need to be reentered and stored.

Example 1: What price should you pay on August 28, 2004 for a $5^1/_2$ % bond (computed with a 30/360 basis) that matures on June 1, 2008, if you want a yield of $7^3/_4$ %? What price should you pay for a yield of 8%? This problem assumes a redemption value of 100.

Keystrokes	Display	
STOEEX		Set compound interest mode if the C indicator is not on.
5.5STO 2	5.50	Coupon into register 2.
8.282004STO3	8.28	Settlement date into register 3.
6.012008STO4	6.01	Maturity date into register 4.
100sto5	100.00	Redemption value into register 5.
7.75 STO 0	7.75	Yield into register 0.
R/S	92.77	Price (calculated).
X≷Y	1.33	Accrued interest (calculated).
8ST00	8.00	New yield into register 0.
R/S	92.01	Price to yield 8% (calculated).
X≷Y	1.33	Accrued interest (calculated).
+	93.34	Total price paid.

Example 2: The market is quoting $93^3/_8\%$ for the bond described in example 1. What yield will that provide? What would be the yield to maturity if 92% were the quoted price?

Keystrokes	Display	
	93.34	From previous example.
OSTO O		
3ENTER8÷		
93+ST01R/S	7.55	Yield at $93^3/_8\%$ (calculated).
92STO 1 R/S	8.00	Yield at 92% (calculated).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 165 of 209

Annual Coupon Bonds

For bonds which have annual coupons, use the following hp 12c program to evaluate price and accrued interest on an Actual/Actual day basis. This program may be modified for annual coupon bonds to be calculated on a 30/360 day basis.

KEYSTROKES	I	DISPLAY		KEYSTROKES	D	ISPLAY	
f P/R				g ADYS	19-	43	26
f CLEAR PRGM	00-			STO7	20-	44	7
f CLEAR FIN	01-	42	34	RCL 6	21-	45	6
g END	02-	43	8	RCL 4	22-	45	4
RCL 0	03-	45	0	g ADYS	23-	43	26
n	04-		11	RCL 7	24-	45	7
RCL 2	05-	45	2	÷	25-		10
PMT	06-		14	n	26-		11
RCL 1	07-	45	1	0	27-		0
i	08-		12	PMT	28-		14
RCL 3	09-	45	3	FV	29-		15
FV	10-		15	CHS	30-		16
PV	11-		13	RCL n	31-	45	11
RCL 5	12-	45	5	RCL 2	32-	45	2
EEX	13-		26	CHS	33-		16
6	14-		6	X	34-		20
CHS	15-		16	R/S	35-		31
	16-		30	_	36-		30
STO 6	17-	44	6	f P/R			
RCL 5	18-	45	5				

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 166 of 209

REGISTERS					
n: Used	i: Yield	PV: Used	PMT: Cpn. or 0		
FV: Used	R _o : # Periods (n)	R ₁ : Yield	R ₂ : Coupon		
R ₃ : Redemption	R ₄ : Settlement	R ₅ : Next Cpn.	R ₆ : Last Coupon		
R ₇ : Used	R ₈ -R _{.5} : Unused				

For annual coupon bonds calculated on a 30/360 day basis, insert \overline{R} after \overline{g} \overline{ADYS} at steps 19 and 23 (making the program two steps longer).

- 1. Key in the program and press STO EEX if the **C** status indicator is not displayed.
- 2. Key in the total number of coupons which are received and press STOO.
- 3. Key in the annual yield as a percentage then press STO 1.
- 4. Key in the amount of the annual coupon then press 502.*
- 5. Key in the redemption value then press STO 3.*
- 6. Key in the settlement (purchase) date† then press STO 4.
- 7. Key in the date of the next coupon then press STO 5.
- 8. Press R/S to obtain the amount of accrued interest.
- 9. Press R/S to determine the price of the bond.
- 10. For a new case, return to step 2.


Example: What is the price and accrued interest of a 20-year Eurobond with annual coupons of 6.5% purchased on August 15, 2004 to yield 7%. The next coupon is received on December 1, 2004.

Keystrokes	Display	
STOEEX		Set compound interest mode if the C indicator is not on.
20STO 0	20.00	Total number of coupons.
7 <u>STO</u> 1	7.00	Annual yield.
6.5STO2	6.50	Annual coupon rate.
100STO3	100.00	Redemption value.
8.152004STO4	8.15	Settlement date.
12.012004STO5	12.01	Next coupon date.
R/S	-4.58	Accrued interest.
R/S	-94.75	Purchase price.

^{*} Positive for cash received; negative for cash paid out.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 167 of 209

⁺ For information about date format see pages 29 to 30.



File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Page: 169 of 209

Dimension: 14.8 cm x 21 cm

Appendix A

The Automatic Memory Stack

Four special registers in the hp 12c are used for storing Z numbers during calculations. To understand how these Υ registers are used, they should be visualized as stacked on top of each other. Displayed X

(For this reason, they are generally referred to as the "stack registers" or collectively as "the stack.") The stack registers are designated X, Y, Z, and T. Unless the calculator is in Program mode, the number shown in the display is the number in the X-register (modified according to the current display format).

The number in the X-register - and, for two-number functions, the number in the Y-register — are the number(s) used in calculations. The Z- and T-registers are used primarily for the automatic retention of intermediate results during chain calculations, as described in section 1.

Before we discuss the details of the stack operation, let's take a quick look at how the stack is used in a simple arithmetic calculation and in a chain calculation. For each key pressed in the keystroke sequence, the diagram illustrating the calculation shows, above the key, the numbers in each of the stack registers after that key is pressed.

First, let's consider the calculation of 5-2:

т →	0	0	0	0
z 🗪	0	0	0	0
Y →	0	5	5	0
Displayed X –	5	5	2	3
Keys -	5	ENTER	2	

The diagram shows why we said in section 1 that the ENTER key separates the second number entered from the first number entered. Note also that this positions the 5 in the Y-register above the 2 in the X-register — just like they would be positioned if you wrote the calculation vertically on paper:

170

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 170 of 209 Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

Appendix A: The Automatic Memory Stack 171

Now let's see what happens in the stack during a chain calculation:

	$(3\times4)+(5\times6)$											
						7						
т 🗕	-	0	0	0	0	0	0	0	0	0	0	0
z 🗕	-	0	0	0	0	0	12	12	0	0	0	0
Y —		0	3	3	0	12	5	5	12	0	42	0
x →	-	3	3	4	12	5	5	6	30	42	7	6
Key 🚽	-	3	ENTER	4	x	5	♠	6	х	+	7	÷
		- 1	ENTER	J			ENTER					

Page: 171 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

172 Appendix A: The Automatic Memory Stack

Termination of Digit Entry

The first digit keyed in after digit entry has been terminated *replaces* the number already in the displayed X-register. Digit entry is automatically terminated when any key is pressed (except for digit entry keys — digit keys, \bullet , CHS, and EEX — and prefix keys — f, g,STO, RCL, and GTO).

Stack Lift


When the stack lifts, the number in each stack register is copied into the register above, and the number formerly in the T-register is lost. The number formerly in the X-register is then contained in both the X-register and the Y-register.

When a number is entered into the displayed X-register — either from the keyboard, from a storage register (using $\overline{\mathbb{RCL}}$), or from the LAST X register (using $\overline{\mathbb{RSTX}}$) — the stack *usually* lifts first. The stack does *not* lift if the last key pressed before a number is entered was one of the following: $\overline{\mathbb{RNE}}$, $\overline{\mathbb{CLX}}$, $\overline{\mathbb{E}}$, $\overline{\mathbb{E}}$, $\overline{\mathbb{E}}$, $\overline{\mathbb{E}}$, or $\overline{\mathbb{E}}$ or $\overline{\mathbb{E}}$.* If one of these keys was the last key pressed, the number in the displayed X-register is replaced when a new number is entered.

Rearranging Numbers in the Stack

The X≥y key


Pressing \nearrow exchanges the numbers in the X- and Y-registers.



Certain functions ($\boxed{\text{ADYS}}$, $\boxed{\text{INT}}$, $\boxed{\text{AMORT}}$, $\boxed{\text{PRICE}}$, $\boxed{\text{SL}}$, $\boxed{\text{SOYD}}$, $\boxed{\text{DB}}$, $\boxed{\overline{\textbf{x}}}$, $\boxed{\text{S}}$, $\boxed{\text{$\widehat{\textbf{y}}$,r}}$, and $\boxed{\text{$\widehat{\textbf{x}}$,r}}$) return answers to the Y-register as well as to the displayed X-register. The $\boxed{\text{xzy}}$ key, since it exchanges the number in the Y-register with that in the displayed X-register, is used to display the second number calculated.

The R↓ Key


When \mathbb{R}^{\downarrow} (roll down) is pressed the number in each stack register is copied into the register below, and the number formerly in the X-register is copied into the T-register.



^{*} In addition, the stack does not lift when a number is entered if the last operation performed was storing a number into a financial register. For example, the stack will *not* lift when a number is entered following the sequence 100000 PV, but will lift when a number is entered following the sequence 100000 PV FV. Note also that although the stack lifts when INTER is pressed, it does not lift when a number is entered after INTER is pressed.


File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 172 of 209

Pressing RJ four times successively displays the numbers in the Y-, Z-, and T-registers and returns the numbers to their original registers.



One-Number Functions and the Stack

One-number mathematics and number-alteration functions $-\sqrt[y]{x}$, \sqrt{x} , \sqrt{x} , \sqrt{x} , \sqrt{x} $\boxed{\text{n!}}$, $\boxed{\text{RND}}$, $\boxed{\text{INTG}}$, and $\boxed{\text{FRAC}}$ — use only the number in the displayed X-register. When the key is pressed, the function is performed upon the number in the X-register, and the answer is then placed into the X-register. The stack does not lift, so the number formerly in the X-register does not get copied into the Y-register; but this number is copied into the LAST X register. The numbers in the Y-, Z-, and T-registers are not affected when a one number function is performed.



Two-Number Functions and the Stack

Two-number functions -+, -, \times , \div , y^x , %, $\Delta\%$, and %T - use the numbers in both the X- and the Y-registers.

Mathematics Functions

To perform an arithmetic operation, the numbers are positioned in the X- and Y-registers just as you would write them vertically on paper: the number you would write on top goes in the Y-register, and the number you would write on the bottom goes in the X-register. For example, to do each of the four arithmetic calculations shown below, you would put the 8 in the Y-register (using INTER) and then key the 2 into the displayed X-register.)


File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 173 of 209

174 Appendix A: The Automatic Memory Stack

Addition	Subtraction	Multiplication	Division
8	8	8	8
+2	-2	×2	2


When an arithmetic operation or y^X is performed, the answer is placed in the X-register, the number formerly in the X-register is copied into the LAST X register, and the stack *drops*. When the stack drops, the number in the Z-register is copied into the Y-register, and the number in the T-register is copied into the Z-register *but also* remains in the T-register.

The diagram on the next page illustrates the stack operation when $8 \div 2$ is calculated. (Assume that the stack and LAST X registers have already been loaded with the numbers shown as the result of previous calculations.)



Percentage Functions

When any of the three percentage functions is performed, the answer is placed in the X-register, the number formerly in the X-register is copied into the LAST X register, but the stack does not drop. The numbers in the Y-, Z-, and T-registers are not changed when a percentage function is performed.



File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 174 of 209

Calendar and Financial Functions

The following table shows what quantity is in each stack register after the indicated calendar or financial function key is pressed. The symbols x, y, z, and t represent the number that was in the corresponding register (X, Y, Z, or T, respectively) at the time the function key was pressed.

Register	DATE	ΔDYS	[INT]	n, i, PV, PMT, FV, NPV, IRR*	AMORT
T	t	t	х	t	у
Z	t	Z	INT ₃₆₅	Z	x (number of payments)
Υ	Z	$\Delta DYS_{ ext{30-day}}$	–PV	У	PMT _{PRIN}
Х	DATE	$\Delta DYS_{\mathit{actual}}$	INT ₃₆₀	n, i, PV, PMT, FV, NPV, IRR	PMT _{INT}

Register	PRICE	[YTM]	SL, SOYD, DB
T	y (settlement date)	Z	у
Z	x (maturity date)	y (settlement date)	x (number of year)
Y	INT	x (maturity date)	RDV (remaining depreciable value)
Х	PRICE	YTM	DEP

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 175 of 209


^{*} For \(\bar{n}\), \(\bar{i}\), \(\bar{PV}\), \(\bar{PMT}\), and \(\bar{FV}\), the stack registers hold the quantities shown if the key is pressed to calculate the corresponding quantity rather than to merely store a number in the corresponding register.

The LAST X Register and the LSTX Key

The number in the displayed X-register is copied into the **LAST X** register whenever any of the following function keys is pressed:

+		X	÷	1/x
y^x	e ^x	LN	$\sqrt{\overline{x}}$	RND
FRAC	INTG	Σ+	Σ-	x,r
ŷ,r	n!	%	Δ%	%T
DATE	ΔDYS			

Pressing GLSTx lifts the stack (unless $\overline{\mathbb{NTH}}$, $\overline{\mathbb{CLx}}$, $\overline{\Sigma}$, $\overline{\mathbb{L}2X}$, or $\overline{\mathbb{L}2X}$ was the last key pressed, as described on page 172), then copies the number from the LAST X register into the displayed X-register. The number remains also in the LAST X register.



Chain Calculations

The automatic stack lift and stack drop make it possible to do chain calculations without the necessity for keying in parentheses or storing intermediate results, as are required on some other calculators. An intermediate result in the displayed X-register is automatically copied into the Y-register when a number is keyed in after a function key is pressed.* Therefore, when a two-number function key is then pressed, that function is performed using the number keyed into the displayed X-register and the intermediate result in the Y-register. The number then in the Y-register, if remaining as an intermediate result from an earlier calculation, can then be used with the intermediate result in the X-register for another calculation.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 176 of 209

^{*} Except for NTE, CLX, Σ±, ΣΞ, 12X or 12±, and — under certain circumstances — \(\bar{n}\), \(\bar{i}\), \(\bar{pV}\), \(\bar{pMT}\), and \(\bar{FV}\). For more information, refer to Stack Lift, page 172.

The diagram on page 171 illustrates how the automatic stack lift and stack drop make chain calculations quick and error-free.

Virtually every chain calculation you are likely to encounter can be done using only the four stack registers. However, to avoid having to store an intermediate result in a storage register, you should begin every chain calculation at the innermost number or pair of parentheses and then work outward — just as you would if you were doing the calculation manually (that is, using pencil and paper). For example, consider the calculation of

$$3[4+5(6+7)]$$

If this calculation were done from left to right — as were the (simpler) examples under Chain Calculations on page 20 and page 22 — you would have to enter five numbers into the calculator before doing the first operation possible (6 + 7). But since the stack holds only four numbers, this calculation cannot be done left-to-right. However, it can easily be done if you begin with the calculation in the innermost pair of parentheses — again, (6 + 7).

Keystrokes	Display	
6ENTER 7 (+)	13.00	Intermediate result of (6+7).
5×	65.00	Intermediate result of 5 (6+7).
4+	69.00	Intermediate result of $[4 + 5(6 + 7)]$.
3×	207.00	Final result: 3 [4 + 5 (6 + 7)].

Arithmetic Calculations with Constants

Because the number in the T-register remains there when the stack drops, this number can be used as a constant in arithmetic operations. To place the constant into the T-register, key it into the display (that is, into the X-register), then press three times. This also places the constant in the Y and Z-registers. Each time an arithmetic operation is then performed — using the constant in the Y-register and a number keyed into the displayed X-register — the constant will be "dropped" back into the Y-register.

Example: The annual sales of solar engineering hardware your firm — currently \$84,000 — are projected to double each year for the next 3 years. Calculate the annual sales for each of those years.

Keystrokes	Display	
2 ENTER ENTER		
ENTER	2.00	Enters constant into Y, Z, and
		T-registers.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 177 of 209

178 Appendix A: The Automatic Memory Stack

Keystrokes	Display	
84000	84,000.	Enters base amount into displayed X-register.
X	168,000.00	Annual sales after first year.
X	336,000.00	Annual sales after second year.
X	672,000.00	Annual sales after third year.

In the example above, the constant was repeatedly multiplied by the result of the previous operation, which was already in the displayed X-register. In another class of calculations with constants, the constant is multiplied by (or added to, etc.) a new number keyed into the displayed X-register. For these calculations, you must press CLx before keying in a new number after having pressed an operator key. If this were not done, the stack would lift when you keyed in a new number after pressing the operator key, and the Y-register would no longer contain the constant. (Recall — from page 172 — that the stack does not lift when a number is keyed into the displayed X-register after CLx is pressed.)

Example: At Permex Pipes a certain pipe fitting is packaged in quantities of 15, 75, and 250. If the cost per fitting is \$4.38, calculate the cost of each package.*

Keystrokes	Display	
4.38 ENTER ENTER		
ENTER	4.38	Enters constant into Y-, Z-, and T-registers.
15	15.	Enters first quantity into displayed X-register.
X	65.70	Cost of a package of 15.
CLx 75	75.	Clears display and enters second quantity into displayed X-register.
X	328.50	Cost of a package of 75.
CLx 250	250.	Clears display and enters third quantity into displayed X-register.
X	1,095.00	Cost of a package of 250.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 178 of 209

^{*} You may want to compare this method of arithmetic calculations with constants to the method using LSTX described on page 74.

Appendix B

More About IRR

Given a sequence of positive and negative cash flows, we hope that there is enough information to determine whether an *IRR* answer exists, and what that answer is. For the vast majority of cases, your hp 12c will find the unique *IRR* answer if it exists. But the *IRR* computation is so complex that if the cash flow sequence does not meet certain criteria, then sometimes the calculator is unable to determine whether or not an answer or answers exist.

Let's look at all of the possible outcomes of IRR as calculated by your hp 12c:

Case 1: A positive answer. If a positive answer is displayed, it is the only such answer. One or more negative answers may also exist.

Case 2: A negative answer. If a negative answer is displayed, there *may* be additional negative answers, and there *may* be a single positive answer. If additional answers (negative or positive) exist, they can be calculated using the procedure described below.

Case 3: The calculator displays **Error 3**. This indicates that the computation is very complex, possibly involving multiple answers, and cannot be continued until you give the calculator an estimate of *IRR*. The procedure for doing so is described below.

Case 4: The calculator displays **Error 7**. This indicates that there is no answer to the computation of *IRR* with the cash flow amounts you have entered. This situation is probably the result of a mistake in entering the magnitudes or signs of the cash flows or the number of times a cash flow amount occurs consecutively. Refer to Reviewing Cash Flow Entries (page 64) and Changing Cash Flow Entries (page 65) to check and correct the entries. **Error 7** will result if there is not at least one positive cash flow *and* at least one negative cash flow.

Although the calculator will eventually reach one of the above outcomes, it may take a long time to get there. You may wish to terminate the *IRR* iterative process, by pressing any key, to see what interest rate the calculator has computed at that point. If you stop the calculation, you may continue searching for *IRR* as described below.

Searching for IRR. You can continue searching for IRR solutions, even after an **Error 3** indication, as follows:

- 1. Make a guess for the interest rate and key it in.
- 2. Press RCL g R/S.

179

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 179 of 209

180 Appendix B: More About IRR

Your guess will aid the calculator in its search, and if it finds an *IRR* answer near your guess, that answer will be displayed. Since the calculator cannot tell you the number of solutions that exist when there is more than one mathematically correct answer, you can continue to make guesses, pressing RCL 9 R/S after each one, to search for *IRR* solutions.

You can hasten this process by using the NPV function to help you make a good guess. Remember that a correct *IRR* solution will make the calculated *NPV* very small. So continue to guess interest rates and solve for *NPV* until the answer you obtain is reasonably close to zero. Then press RCL 9 R/S to calculate the *IRR* answer near your guess.

How would this work in case 2 above? The calculator displays a negative answer and you wish to check for a unique positive *IRR*. Key in successively larger guesses for *i* (starting from 0) and solve for *NPV* until you reach a sign change in your *NPV* outcomes. Then press RCL 9 R/S to find an *IRR* solution near the last interest rate obtained using the NPV key.

If you stop the *IRR* iterative process, you can test the interest obtained using \overline{NPV} , and then restart the process by pressing $\overline{RCLgR/S}$.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 180 of 209

Appendix C

Error Conditions

Some calculator operations cannot be performed under certain conditions (for example, \div when x = 0). If you attempt such an operation under these conditions, the calculator will display the word **Error** followed by a digit, **0** through **9**. Listed below are operations that cannot be performed under the conditions specified. The symbols x and y represent the number in the X- and Y-registers, respectively, when the operation key is pressed.

Error 0: Mathematics

Operation	Condition
÷	<i>x</i> = 0
<i>\\x</i>	<i>x</i> = 0
\sqrt{x}	<i>x</i> < 0
LN	<i>x</i> ≤ 0
y^x	$y = 0$ and $x \le 0$
	y < 0 and x is noninteger.
Δ%	<i>y</i> = 0
\(\mathbb{T}\)	<i>y</i> = 0
STO ÷ (0 through 4)	<i>x</i> = 0
n!	x is noninteger
	<i>x</i> < 0

181

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 181 of 209

Error 1: Storage Register Overflow

Operation

Condition

STO + (0	through 4)
	through 4)
STO X (0	through 4)
STO ÷ (0	through 4)
12x	

Magnitude of result is greater than 9.999999999×10^{99} .

Error 2: Statistics

Operation

Condition

$$\begin{array}{ll} \overline{\mathbb{X}} & & & & & & & \\ \overline{\mathbb{X}} w & & & & & & \\ \overline{\mathbb{X}} w & & & & & \\ \overline{\mathbb{X}} x = 0 & & & \\ \overline{\mathbb{X}} & & & & \\ \overline{\mathbb{X}} & & & & \\ \overline{\mathbb{X}} & & & & \\ \hline{\mathbb{X}} & & & & \\ \overline{\mathbb{X}} & & & \\ \overline{\mathbb{X}} & & & \\ \hline{\mathbb{X}} & &$$

Error 3: IRR

Refer to Appendix B.

Error 4: Memory

- Attempting to enter more than 99 program lines.
- Attempting to GTO to a program line that does not exist.
- Attempting storage register arithmetic in R_5 through R_9 or R_0 through R_9 .

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 182 of 209

Error 5: Compound Interest

Operation	Condition
n	$PMT \le -PV \times i$ $PMT = FV \times i$ $i \le -100$ The values in i, PV, and FV are such that no solution exists for n .
i	PMT = 0 and $n < 0Cash flows all have same sign.$
PV	$i \leq -100$
[PMT]	$n = 0$ $i = 0$ $i \le -100$
FV	$i \leq -100$
AMORT	$x \le 0$ x is noninteger.
NPV	$i \le -100$
SL SOYD DB	$n \le 0$ $n > 10^{10}$ $x \le 0$ x = 0

Error 6: Storage Registers

Operati	on	Condition
STO RCL	}	Storage register specified does not exist or has been converted to program lines.
CF _j	}	n specifies a storage register that does not exist or has been converted to program lines.
NPV IRR	}	n > 20 n > r (as defined by MEM) n < 0 n is noninteger
Nj		x > 99 x < 0 x is noninteger

Page: 183 of 209

File name: hp 12c_user's guide_English_HDPMBF12E44
Printered Date: 2005/7/29 Dimension: 14.8 cm x 21 cm

184 Appendix C: Error Conditions

Error 7: IRR

Refer to Appendix B.

Error 8: Calendar

Condition **Operation** ΔDYS Improper date format or illegal date. DATE DATE Attempting to add days beyond calculator's date capacity. PRICE Improper date format or illegal date. YTM More than 500 years between settlement (purchase) date and maturity (redemption) date. Maturity date earlier than settlement date. Maturity date has no corresponding coupon date (6 months earlier).*

Error 9: Service

Refer to Appendix E.

Pr Error

- Continuous Memory has been reset. (Refer to Continuous Memory, page 70.)
- You have reset the calculator using the reset hole (see page 194).

To correct this problem for all maturity dates except August 29 and 30, add one day to *both* the settlement date *and* the maturity date in your calculations. For instance, if a bond were purchased on June 1, 2004 (the settlement date) with a maturity date of December 31, 2005, you should change the dates to June 2, 2004 and January 1, 2006 for your calculations. For August 29 and 30, there is no calculator solution that gives the correct answer.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 184 of 209

^{*} This is the case for the 31st of March, May, August, October, and December, plus August 29 (except in a leap year) and 30. For example, there is no September 31, so March 31 has no corresponding coupon date 6 months earlier.

Appendix D

Formulas Used

Percentage

$$\% = \frac{\text{Base}(y) \times \text{Rate}(x)}{100}$$

$$\Delta\% = 100 \left(\frac{\text{NewAmount}(x) - \text{Base}(y)}{\text{Base}(y)} \right)$$

$$\%T = 100 \left(\frac{\text{Amount}(x)}{\text{Total}(y)} \right)$$

Interest

n =number of compounding periods.

i = periodic interest rate, expressed as a decimal.

PV = present value.

FV = future value or balance.

PMT = periodic payment.

S = payment mode factor (0 or 1) indicating treatment of *PMT*.O corresponds to End, 1 to Begin.

I = interest amount.

INTG (n) = integer portion of n.

FRAC (n) = fractional portion of n.

Simple Interest

$$I_{360} = \frac{n}{360} \times PV \times i$$

$$I_{365} = \frac{n}{365} \times PV \times i$$

186 Appendix D: Formulas Used

Compound Interest

Without an odd period:

$$O = PV + (1+iS) \cdot PMT \cdot \left[\frac{1 - (1+i)^{-n}}{i} \right] + FV(1+i)^{-n}$$

With simple interest used for an odd period:

$$O = PV[1 + iFRAC(n)] + (1 + iS)PMT \left[\frac{1 - (1 + i)^{-INTG(n)}}{i} \right] + FV(1 + i)^{-INTG(n)}$$

With compound interest used for an odd period:

$$0 = PV(1+i)^{FRAC(n)} + (1+iS)PMT \left[\frac{1 - (1+i)^{-INTG(n)}}{i} \right] + FV(1+i)^{-INTG(n)}$$

Amortization

n = number of payment periods to be amortized.

 INT_i = amount of *PMT* applied to interest in period *j*.

 PRN_i = amount of PMT applied to principal in period j.

 PV_i = present value (balance) of loan after payment in period j.

j = period number.

 $INT_1 = \{0 \text{ if } n = 0 \text{ and payment mode is set to Begin.} \}$

 $|PV_0 \times i|_{RND}$ (sign of PMT)

 $PRN_1 = PMT - INT_1$

 $PV_1 = PV_0 + PRN_1$

 $INT_i = |PV_{i-1} \times i|_{RND} \times \text{(sign of } PMT\text{) for } j > 1.$

 $PRN_{i} = PMT - INT_{i}$

 $PV_i = PV_{i-1} + PRN_i$

$$\sum INT = \sum_{j=1}^{n} INT_{j} = INT_{1} + INT_{2} + \dots + INT_{n}$$

$$\sum PRN = \sum_{j=1}^{n} PRN_{j} = PRN_{1} + PRN_{2} + \dots + PRN_{n}$$

$$PV_n = PV_0 + \sum PRN$$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 186 of 209

Discounted Cash Flow Analysis

Net Present Value

NPV = net present value of a discounted cash flow. $CF_i = cash flow at period j$.

NPV =
$$CF_0 + \frac{CF_1}{(1+i)^1} + \frac{CF_2}{(1+i)^2} + \dots + \frac{CF_n}{(1+i)^n}$$

Internal Rate of Return

n = number of cash flows $CF_i = \text{cash flow at period } j$.

IRR = Internal Rate of Return

$$0 = \sum_{j=1}^{k} CF_{j} \cdot \left[\frac{1 - (1 + IRR)^{-n_{j}}}{IRR} \right] \cdot \left[(1 + IRR)^{-\sum_{q < j} nq} \right] + CF_{0}$$

Calendar

Actual Day Basis

 $\Delta DYS = \bar{f}(DT_2) - f(DT_1)$ f(DT) = 365 (yyyy) + 31 (mm - 1) + dd + INTG (z/4) - xand for $mm \le 2$ x = 0z = (yyyy) - 1for mm > 2x = INTG (0.4mm + 2.3)z = (yyyy)INTG = Integer portion.

Note: Additional tests are performed in order to ensure that the century (but not millennium) years are not considered leap years.

30/360 Day Basis

DAYS =
$$f(DT_2) - f(DT_1)$$

 $f(DT) = 360 (yyyy) + 30mm + z$
for $f(DT_1)$
if $dd_1 = 31$ then $z = 30$
if $dd_1 \neq 31$ then $z = dd_1$
for $f(DT_2)$
if $dd_2 = 31$ and $dd_1 = 30$ or 31 then $z = 30$
if $dd_2 = 31$ and $dd_1 < 30$ then $dd_2 < 30$ then $dd_2 < 31$ then $dd_2 < 31$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 187 of 209

188 Appendix D: Formulas Used

Bonds

Reference:

Spence, Graudenz, and Lynch, *Standard Securities Calculation Methods*, Securities Industry Association, New York, 1973.

DIM = days between issue date and maturity date.

DSM = days between settlement date and maturity date.

DCS = days between beginning of current coupon period and settlement date.

E = number of days in coupon period where settlement occurs.

DSC = E - DCS =days from settlement date to next 6-month coupon date

N = number of semiannual coupons payable between settlement date and maturity date.

CPN = annual coupon rate (as a percentage).

YIELD = annual yield (as a percentage).

PRICE = dollar price per \$100 par value.

RDV = redemption value.

For semiannual coupon with 6 months or less to maturity:

$$PRICE = \left[\frac{100(RDV + \frac{CPN}{2})}{100 + (\frac{DSM}{E} \times \frac{YIELD}{2})} \right] - \left[\frac{DCS}{E} \times \frac{CPN}{2} \right]$$

For semiannual coupon with more than 6 months to maturity:

$$PRICE = \left[\frac{RDV}{\left(1 + \frac{YIELD}{200}\right)^{N-1 + \frac{DSC}{E}}} \right] + \left[\sum_{K=1}^{N} \frac{\frac{CPN}{2}}{\left(1 + \frac{YIELD}{200}\right)^{K-1 + \frac{DSC}{E}}} \right] - \left[\frac{CPN}{2} \times \frac{DCS}{E} \right]$$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 188 of 209

Depreciation

L = asset's useful life expectancy.

SBV = starting book value.

SAL = salvage value.

FACT = declining-balance factor expressed as a percentage.

j = period number.

 DPN_i = depreciation expense during period j.

 RDV_i = remaining depreciable value at end of period i = $RDV_{i-1} - DPN_i$ where $RDV_0 = SBV - SAL$

 RBV_i = remaining book value = RBV_{i-1} - DPN_i where RBV_0 = SBV

 Y_{i} = number of months in partial first year.

Straight-Line Depreciation

Keyboard function:

$$DPN_{j} = \frac{SBV - SAL}{I}$$
 for $j = 1, 2, ..., L$

Program for partial first year:

$$DPN_{1} = \frac{SBV - SAL}{L} \cdot \frac{Y_{1}}{12}$$

$$DPN_{j} = \frac{SBV - SAL}{L} \text{ for } j = 2, 3, ..., L$$

$$DPN_{j+1} = RDV_{j}$$

Sum-of-the-Years-Digits Depreciation

$$SOYD_k = \frac{(W+1)(W+2F)}{2}$$

where W = integer part of k

F = fractional part of k

(i.e., for k = 12.25 years, W = 12 and F = 0.25).

Keyboard function:

$$DPN_J = \frac{(L-j+1)}{SOYD_I} \cdot (SBV - SAL)$$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 189 of 209

190 Appendix D: Formulas Used

Program for partial year:

$$\begin{aligned} DPN_1 &= \left(\frac{L}{SOYD}\right) \cdot \left(\frac{Y_1}{12}\right) \cdot (SBV - SAL) \\ DPN_j &= \left(\frac{LADJ - j + 2}{SOYD_{LADJ}}\right) \cdot (SBV - D_1 - SAL) & \text{for } j \neq 1 \\ \text{where } LADJ = L - \left(\frac{Y_1}{12}\right) \end{aligned}$$

Declining-Balance Depreciation

Keyboard function:

$$DPN_{j} = RBV_{j-1} \cdot \frac{FACT}{100L}$$
 for $j = 1, 2, ..., L$

Program for partial first year:

$$DPN_{1} = SBV \cdot \frac{FACT}{100L} \cdot \frac{Y_{1}}{12}$$

$$DPN_{j} = RBV_{j-1} \cdot \frac{FACT}{100L} \text{ for } j \neq 1$$

Modified Internal Rate of Return

n =number of compounding periods.

 NFV_{p} = Net future value of the positive cash flows.

 NPV_N = Net present value of the negative cash flows.

$$MIRR = 100 \left[\left(\frac{NFV_p}{-NPV_N} \right)^{\frac{1}{n}} - 1 \right]$$

Advance Payments

A = number of payments made in advance.

$$PMT = \frac{PV - FV(1+i)^{-n}}{\left[\frac{1 - (1+i)^{-(n-A)}}{i} + A\right]}$$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 190 of 209

Interest Rate Conversions

C = number of compounding periods per year.

EFF = the effective annual interest rate as a decimal.

NOM = the nominal annual interest rate as a decimal.

Finite Compounding

$$EFF = \left(1 + \frac{NOM}{C}\right)^{C} - 1$$

Continuous Compounding

$$EFF = (e^{NOM} - 1)$$

Statistics

$$\overline{x} = \frac{\sum x}{n}$$
 $\overline{y} = \frac{\sum y}{n}$

Weighted Mean

$$\overline{x}_w = \frac{\sum wx}{\sum w}$$

Linear Estimation

n = number of data pairs

$$\hat{y} = A + Bx$$

$$\hat{x} = \frac{y - A}{B}$$

where
$$B = \frac{\sum xy - \frac{\sum x \cdot \sum y}{n}}{\sum x^2 - \frac{(\sum x)^2}{n}}$$

$$A = \overline{y} - B\overline{x}$$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 191 of 209

192 Appendix D: Formulas Used

$$r = \frac{\left[\sum xy - \frac{\sum x \cdot \sum y}{n}\right]}{\sqrt{\left[\sum x^2 - \frac{(\sum x)^2}{n}\right] \cdot \left[\sum y^2 - \frac{(\sum y)^2}{n}\right]}}$$

Standard Deviation

$$s_x = \sqrt{\frac{n\sum x^2 - (\sum x)^2}{n(n-1)}}$$
 $s_y = \sqrt{\frac{n\sum y^2 - (\sum y)^2}{n(n-1)}}$

Factorial

0! = 1

For n > 1 where n is an integer:

$$n! = \prod_{i=1}^{n} i$$

The Rent or Buy Decision

Market Value = $PRICE(1 + I)^n$

where:

I = appreciation per year (as decimal)

n = number of years

Net Cash Proceeds on Resale = Market Value - Mortgage Balance - Commission

The interest rate is obtained by solving the financial (compound interest) equation for i using:

n = number of years house is owned

PV = down payment + closing costs

PMT = mortgage payment + taxes + maintenance - rent - (% tax)

(interest + taxes)

FV = net cash proceeds on resale

Annual interest rate = $12 \times i$

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 192 of 209

Appendix E

Battery, Warranty, and Service Information

Battery

The hp 12c is shipped with one 3 Volt CR2023 Lithium battery. Battery life depends on how the calculator is used. If the calculator is being used to perform operations other than running programs, it uses much less power.

Low-Power Indication

A battery symbol (*) shown in the upper-left corner of the display when the calculator is on signifies that the available battery power is running low. When the battery symbol begins flashing, replace the battery as soon as possible to avoid losing data.

Use only a fresh battery. Do not use rechargeable batteries.

Warning




There is the danger of explosion if the battery is incorrectly replaced. Replace only with the same or equivalent type recommended by the manufacturer. Dispose of used batteries according to the manufacturer's instructions. Do not mutilate, puncture, or dispose of batteries in fire. The batteries can burst or explode, releasing hazardous chemicals. Replacement battery is a Lithium 3V Coin Type CR2032.

Installing a New Battery

The contents of the calculator's Continuous Memory are preserved for a short time while the battery is out of the calculator (provided that you turn off the calculator before removing the battery). This allows you ample time to replace the battery without losing data or programs. If the battery is left out of the calculator for an extended period, the contents of Continuous Memory may be lost.

193

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 193 of 209



the * battery power indicator) should turn on.* If the display shows **Error 9**, goes blank, or otherwise does not show the proper result, the calculator requires service.†

Note: Tests of the calculator's electronics are also performed if the \pm key or the $\dot{\pm}$ key is held down when $\boxed{\tt ON}$ is released.‡ These tests are included in the calculator to be used in verifying that it is operating properly during manufacturing and service.

If you had suspected that the calculator was not working properly but the proper display was obtained in step 2, it is likely that you made an error in operating the calculator. We suggest you reread the section in this handbook applicable to your calculation — including, if appropriate, appendix A. If you still experience difficulty, write or telephone Hewlett-Packard at an address or phone number listed under Service (Page 197).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 195 of 209

^{*} The status indicators turned on at the end of this test include some that normally are not displayed on the hp 12c.

[†] If the calculator displays **Error 9** as a result of the <u>ON/X</u> test or the <u>ON/H</u> test but you wish to continue using your calculator, you should reset Continuous Memory as described on page 70.

[‡] The ON/ → combination initiates a test that is similar to that described above, but continues indefinitely. The test can be terminated by pressing any key, which will halt the test within 25 seconds. The ON/ → combination initiates a test of the keyboard and the display. When the ON key is released, certain segments in the display will be lit. To run the test, the keys are pressed in order from left to right along each row, from the top row to the bottom row. As each key is pressed, different segments in the display are lit. If the calculator is operating properly and all the keys are pressed in the proper order, the calculator will display 12 after the last key is pressed. (The MTE key should be pressed both with the third-row keys and with the fourth-row keys.) If the calculator is not working properly, or if a key is pressed out of order, the calculator will display Error 9. Note that if this error display results from an incorrect key being pressed, this does not indicate that your calculator requires service. This test can be terminated by pressing any key out of order (which will, of course, result in the Error 9 display). Both the Error 9 display and the 12 display can be cleared by pressing any key.

Warranty

hp 12c Financial Calculator; Warranty period: 12 months

- HP warrants to you, the end-user customer, that HP hardware, accessories and supplies will be free from defects in materials and workmanship after the date of purchase, for the period specified above. If HP receives notice of such defects during the warranty period, HP will, at its option, either repair or replace products which prove to be defective. Replacement products may be either new or like-new.
- 2. HP warrants to you that HP software will not fail to execute its programming instructions after the date of purchase, for the period specified above, due to defects in material and workmanship when properly installed and used. If HP receives notice of such defects during the warranty period, HP will replace software media which does not execute its programming instructions due to such defects.
- 3. HP does not warrant that the operation of HP products will be uninterrupted or error free. If HP is unable, within a reasonable time, to repair or replace any product to a condition as warranted, you will be entitled to a refund of the purchase price upon prompt return of the product.
- 4. HP products may contain remanufactured parts equivalent to new in performance or may have been subject to incidental use.
- 5. Warranty does not apply to defects resulting from (a) improper or inadequate maintenance or calibration, (b) software, interfacing, parts or supplies not supplied by HP, (c) unauthorized modification or misuse, (d) operation outside of the published environmental specifications for the product, or (e) improper site preparation or maintenance.
- 6. HP MAKES NO OTHER EXPRESS WARRANTY OR CONDITION WHETHER WRITTEN OR ORAL. TO THE EXTENT ALLOWED BY LOCAL LAW, ANY IMPLIED WARRANTY OR CONDITION OF MERCHANTABILITY, SATISFACTORY QUALITY, OR FITNESS FOR A PARTICULAR PURPOSE IS LIMITED TO THE DURATION OF THE EXPRESS WARRANTY SET FORTH ABOVE. Some countries, states or provinces do not allow limitations on the duration of an implied warranty, so the above limitation or exclusion might not apply to you. This warranty gives you specific legal rights and you might also have other rights that vary from country to country, state to state, or province to province.
- 7. TO THE EXTENT ALLOWED BY LOCAL LAW, THE REMEDIES IN THIS WARRANTY STATEMENT ARE YOUR SOLE AND EXCLUSIVE REMEDIES. EXCEPT AS INDICATED ABOVE, IN NO EVENT WILL HP OR ITS SUPPLIERS BE LIABLE FOR LOSS OF DATA OR FOR DIRECT, SPECIAL, INCIDENTAL, CONSEQUENTIAL (INCLUDING LOST PROFIT OR DATA), OR OTHER DAMAGE, WHETHER BASED IN CONTRACT, TORT, OR OTHERWISE.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 196 of 209

Some countries, States or provinces do not allow the exclusion or limitation of incidental or consequential damages, so the above limitation or exclusion may not apply to you.

8. The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical and editorial errors or omissions contained herein.

FOR CONSUMER TRANSACTIONS IN AUSTRALIA AND NEW ZEALAND: THE WARRANTY TERMS CONTAINED IN THIS STATEMENT, EXCEPT TO THE EXTENT LAWFULLY PERMITTED, DO NOT EXCLUDE, RESTRICT OR MODIFY AND ARE IN ADDITION TO THE MANDATORY STATUTORY RIGHTS APPLICABLE TO THE SALE OF THIS PRODUCT TO YOU.

Service

Europe

Country :	Telephone numbers
Austria	+43-1-3602771203
Belgium	+32-2-7126219
Denmark	+45-8-2332844
Eastern Europe countries	+420-5-41422523
Finland	+35-89640009
France	+33-1-49939006
Germany	+49-69-95307103
Greece	+420-5-41422523
Holland	+31-2-06545301
Italy	+39-02-75419782
Norway	+47-63849309
Portugal	+351-229570200
Spain	+34-915-642095
Sweden	+46-851992065
Switzerland	+41-1-4395358 (German)
	+41-22-8278780 (French)
	+39-02-75419782 (Italian)
Turkey	+420-5-41422523
UK	+44-207-4580161
Czech Republic	+420-5-41422523
South Africa	+27-11-2376200
Luxembourg	+32-2-7126219
Other European countries	+420-5-41422523

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 197 of 209

198 Appendix E: Battery, Warranty, and Service Information

Asia Pacific

Country:	Telephone numbers
Australia	+61-3-9841-5211
Singapore	+61-3-9841-5211

L.America

Country :	Telephone numbers
Argentina	0-810-555-5520
Brazil	Sao Paulo 3747-7799; ROTC
	0-800-157751
Mexico	Mx City 5258-9922; ROTC
	01-800-472-6684
Venezuela	0800-4746-8368
Chile	800-360999
Columbia	9-800-114726
Peru	0-800-10111
Central America &	1-800-711-2884
Caribbean	
Guatemala	1-800-999-5105
Puerto Rico	1-877-232-0589
Costa Rica	0-800-011-0524

N.America

Country:	Telephone numbers
USA	1800-HP INVENT
Canada	(905)206-4663 or
	800-HP INVENT

ROTC = Rest of the country

Please logon to http://www.hp.com for the latest service and support information.

Regulatory Information

This section contains information that shows how the hp 12c financial calculator complies with regulations in certain regions. Any modifications to the calculator not expressly approved by Hewlett-Packard could void the authority to operate the 12c in these regions.

USA

This calculator generates, uses, and can radiate radio frequency energy and may interfere with radio and television reception. The calculator complies with the limits for a Class B digital device, pursuant to Part 15 of the FCC Rules. These limits are designed to provide reasonable protection against harmful interference in a residential installation.

However, there is no guarantee that interference will not occur in a particular installation. In the unlikely event that there is interference to radio or television reception(which can be determined by turning the calculator off and on), the user is encouraged to try to correct the interference by one or more of the following measures:

- Reorient or relocate the receiving antenna.
- Relocate the calculator, with respect to the receiver.

Canada

This Class B digital apparatus complies with Canadian ICES-003.

Cet appareil numerique de la classe B est conforme a la norme NMB-003 du Canada.

Japan

(VCCI)

Temperature Specifications

Operating: 0° to 55° C (32° to 131° F)
 Storage: -40° to 65° C (-40° to 149° F)

Noise Declaration

In the operator position under normal operation (per ISO 7779): LpA < 70dB.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 199 of 209

Disposal of Waste Equipment by Users in Private Household in the European Union



This symbol on the product or on its packaging indicates that this product must not be disposed of with your other household waste. Instead, it is your responsibility to dispose of your waste equipment by handing it over to a designated collection point for the recycling of waste electrical and electronic equipment. The separate collection and recycling of your waste equipment at the time of disposal will help to conserve natural resources and ensure

that it is recycled in a manner that protects human health and the environment. For more information about where you can drop off your waste equipment for recycling, please contact your local city office, your household waste disposal service or the shop where you purchased the product.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 200 of 209

Appendix F

United Kingdom Calculations

The calculations for most financial problems in the United Kingdom are identical to the calculations for those problems in the United States — which are described earlier in this handbook. Certain problems, however, require different calculation methods in the United Kingdom than in the United States, even though the terminology describing the problems may be similar. Therefore, it is recommended that you ascertain the usual practice in the United Kingdom for the financial problem you are solving.

The remainder of this appendix describes three types of financial calculations for which the conventional practice differs significantly between the United Kingdom and the United States.

Mortgages

The amount of the repayments on home loans and mortgages offered by banks in the United Kingdom can usually be calculated as described under Calculating the Payment Amount, page 46. Building Societies in the United Kingdom, however, calculate the amount of these repayments differently. In general, the repayment amount of a Building Society mortgage is calculated as follows: first, the annual repayment amount is calculated using the annual interest rate; second, the periodic repayment amount is calculated by dividing the annual repayment amount by the number of repayment periods in one year.

Furthermore, the calculations used by Building Societies are rounded; therefore, to match their scale repayment figures you would have to round your calculations accordingly.

201

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 201 of 209

Annual Percentage Rate (APR) Calculations

In the United Kingdom, the calculation of the Annual Percentage Rate of Charge (APR) in accordance with the United Kingdom Consumer Credit Act (1974) differs from the calculation of the APR in the United States. Unlike the practice in the United States, where the APR can be calculated by multiplying the periodic interest rate by the number of periods per year, in the United Kingdom the APR is calculated by converting the periodic interest rate to the "effective annual rate," then truncating the result to one decimal place. With the periodic interest rate in the display and in the $\bf i$ register, the effective annual rate can be calculated by keying in the number of compounding periods per year, pressing $\bf n$, then proceeding with step 4 of the procedure given on page 160 for converting a nominal rate to an effective rate.

Bond Calculations

Solutions for the price and yield to maturity of United Kingdom bonds are not included in this handbook. Actual practice differs according to the type of bond; variations such as cumulative and ex-dividend pricing, simple or compound interest discounting, etc., may be encountered.

Application Notes covering such situations may be available in the United Kingdom; check with your local authorized Hewlett-Packard dealer.

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 202 of 209

Function Key Index

General

ON Power on /off key (page 16).

f Shift key. Selects alternate function in gold above the function keys (page 16). Also used in display formatting (page 71).

9 Shift key. Selects alternate function in blue on the slanted face of the function keys (page 16).

CLEAR PREFIX after f, g, STO, RCL or GTO, cancels that key (page 18).

f CLEAR PREFIX also displays mantissa of number in the displayed X-register (page 73).

Digit Entry

ENTER Enters a copy of number in displayed X-register into Y-register. Used to separate numbers (pages 19 and 171).

CHS Changes sign of number or exponent of 10 in X-register (page 17).

EEX Enter exponent. After pressing, next numbers keyed in are exponents of 10 (page 18).

0 —9 digits. Used for keying in numbers (page 19) and display formatting (page 71).

• Decimal point (page 17). Also used for display formatting (page 71).

CLx Clears contents of displayed X-register to zero (page 18).

Arithmetic

 $+-\times \div =$ Arithm etic operators (page 19).

Storage Registers

STO Store. Followed by number key, decimal point and number key, or top row financial key, stores displayed number in storage register specified (page 23). Also used to perform storage register arithmetic (page 24).

RCL Recall. Followed by number key, decimal point and number key, or top-row financial key, recalls value from storage register specified into the displayed X-register (page 23). CLEAR REG Clears contents of stack (X,Y,Z and T), all storage registers, statistical registers, and financial registers (page 24). Leaves program memory untouched; not programmable.

Percentage

% Computes x% of y and retains the y-value in the Y-register (page 26).

△ Computes percent of change between number in Y-register and number in displayed X-register (page 27).

%T Computes percent that x is of number in Y-register (page 28).

Calendar

DMY Sets date format to day-month-year (page 30); not programmable.

M.DY Sets date format to month-day-year (page 29); not programmable.

DATE Changes a date in the Y-register by the number of days in the X-register and displays day of week (page 30).

ADYS Computes the number of days between two dates in the Y and X-registers (page 31).

203

File name: hp 12c_user's guide_English_HDPMBF12E44

Printered Date: 2005/7/29

Page: 203 of 209

Dimension: 14.8 cm x 21 cm

204 Function Key Index

Financial

CLEAR FIN Clears contents of financial registers (page 33).

BEG Sets payment mode to Begin for compound interest calculations involving payments (page 37).

END Sets payment mode to End for compound interest calculations involving payments (page 37).

INT Calculates simple interest (page 33).

n Stores or computes number of periods in financial problem (page 32).

12x Multiplies a number in displayed X-register by 12 and stores the resulting value in the n-register (page 39).

i Stores or computes interest rate per compounding period (page 32).

12÷ Divides number in displayed X-register by 12 and stores the resulting value in the I-register (page 39).

[PV] Stores or computes the present value (that is, the initial cash flow) of a financial problem (page 32).

PMT Stores or computes payment amount (page 32).

FV Stores or computes future value (final cash flow) of a financial problem (page 32).

AMORT Amortizes x number of periods using values stored in PMT, i, PV, and the display. Updates values in PV and n (page 54).

NPV Calculates the net present value of up to 20 uneven cash flows and initial investment using values stored with CFo, CFI, and NI (page 58).

IRR Calculates the internal rate of return (yield) for up to 20 uneven cash flows and initial investment using values stored with CFo, CFj, and Nj

(page 63).

CFo Initial cash flow. Stores contents of displayed X-register in R_0 , initializes n to zero, sets N_0 to 1. Used at the beginning of a discounted cash flow problem (page 58).

CFj Cash flow j. Stores the contents of X-register in R_j, increments n by 1, and sets N_j to 1. Used for all cash flows except the initial cash flow in a discounted cash flow problem (page 58). SL Calculates depreciation using straight-line method. (page 68).

PRICE Calculates bond price, given desired yield to maturity (page 67).

YTM Calculates yield to maturity, given bond price (page 67).

N) Stores the number (from 1 to 99) of times each cash flow occurs as N_i . Assumes 1 unless otherwise specified (page 61).

SOYD Calculates depreciation using sum-of-the-years-digits method (page 68).

DB Calculates depreciation using declining-balance method (page 68).

Statistics

CLEAR Σ Clears statistical storage registers R_1 through R_6 and stack registers (page 76).

∑+ Accumulates statistics using numbers from X- and Y-registers in storage registers R₁ through R₀ (page 76).

Σ- Cancels effect of numbers from X- and Y-registers in storage registers R₁ through R₆ (page 77).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 204 of 209

- X Computes mean (average) of *x-values* and *y-values* using accumulated statistics (page 77).
- Xw Computes weighted average of y-(item) and x-(weight) values using accumulated statistics (page 81).
- S Computes sample standard deviations of *x*-and *y-values* using accumulated statistics **(page 79)**.
- \hat{x} .r Linear estimate (X-register), correlation coefficient (Y-register). Fits a line to a set of (x, y) data pairs entered using Σ^+ , then extra-polates this line to estimate an x-value for a given y-value. Also computes strength of linear relationship (r) among that set of (x, y) data pairs (page 80).

Mathematics

- © Computes square root of number in displayed X-register (page 83).
- Y-register to power of number in X-register (page 85).
- Computes reciprocal of number in displayed X-register (page 83).
- n! Computes factorial [n•(n-1)... 3•2•1] of number in displayed X-register (page 83).
- e Natural antilogarithm. Raises e (approximately 2.718281828) to power of number in displayed X-register (page 83).
- LN Computes natural logarithm (base *e*) of number in displayed X-register (page 83).

Number Alteration

- RND Rounds mantissa of 10digit number in X-register to match the display (page 83).
- INTG Leaves only the integer portion of number in displayed X-register by truncating fractional portion (page 83).
- FRAC Leaves only the fractional portion of number in displayed X-register by truncating integer portion (page 84).

Stack Rearrangement

- Exchanges contents of X and Y-registers of stack (pages 74 and 172).
- RI Rolls down contents of stack for viewing in displayed X-register (page 172).
- LSTX Recalls number displayed before the previous operation back into the displayed X-register (pages 74 and 176).

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 205 of 209

Programming Key Index

P/R Program/Run. Toggles into and out of Program mode. Automatically sets program to line 00 when returning to Run mode (page 86).

MEM Memory map. Describes the current allocation of memory; the number of lines allotted to program memory and the number of available data registers (page 93).

Program Mode

In *Program* mode, function keys are recorded in program memory. Display shows program memory line number and the keycode (keyboard row and location in row) of the function key.

Active Keys:

In Program mode only the following keys are active; they cannot be recorded in program memory.

CLEAR PROM
Clear program. Clears
program memory to all
GTO 00 instructions and
resets calculator so
operations begin at line 00
of program memory. Resets
MEM to P08 r20
(page 95)

Run Mode

In *Run* mode, function keys may be executed as part of a recorded program or individually by pressing from the keyboard.

Pressed from keyboard:

CLEAR (PRGM)
Resets calculator (in Run mode) so operations begin at line 00 of program memory. Does not erase program memory.

Executed as a recorded program instruction

206

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 206 of 209

Program Mode

Active Keys:

GTO Go to. Followed by a decimal point and a two-digit number, positions calculator to that line in program memory. No instructions are executed (page 95)

SST Single step. Displays line number and contents of next program memory line. If held down, displays line number and contents of all program memory lines, one at a time (page 92).

BST Back step. Displays line number and contents of previous program memory line. When back stepped from line 00, goes to end of program memory as defined by 9 MEM. If held down, displays line number and contents of all program memory lines, one at a time (page 95).

Run Mode

Pressed from keyboard:

R/S Run/Stop. Begins execution of a stored program. Stops execution if program is running (page 89).

GTO Go to. Followed by a two-digit number, positions calculator to that line in program memory. No instructions are executed (page 103).

SST Single step. Displays line number and keycode of current program memory line when pressed; executes instruction, displays result, and moves to next line when released (page 96).

BST Back step. Displays line number and keycode of previous program memory line when pressed; displays original contents of X-register when released. No instructions are executed (page 97).

Any key. Pressing any key on the keyboard stops execution of a program (page 102)

Executed as a recorded program instruction:

R/S Run/Stop. Stops program execution (page 101).

GTO Go to. Followed by a two-digit number, causes calculator to branch to the specified line number next, and resumes program execution from there (page 103).

PSE Pause. Stops program execution for about 1 second and displays contents of X-register, then resumes program execution (page 97).

 $x \in y$ x = 0 Conditional. x≤y tests number in X-register against that in Y-register. x=0 tests number in X-register against zero. If true, calculator continues execution at next program memory line. If false, calculator skips next line before resuming execution (page 107)

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 207 of 209

Subject Index

Bonds, municipal, 67 Bonds, state and local government, AMORT, 12, 54, 172 Bonds, U.S. Treasury, 66 Adding instructions, 114-19 Branching, 103-12, 116 Advance payments, 151, 156 Branching, adding instructions by, Amortization, 38, 54-56, 186 116–19 Annual interest rate, 39 Branching, conditional, 107-8 Annual Percentage Rate, 52-53, Branching, simple, 103 124-26, 202 Annuities, 36 C Annuities, deferred, 134-35 CFo, 61 Annuity due, 37-38 CFi, 59, 61, 64 Appreciation, 38 APR. See Annual Percentage Rate CHS, 17, 19, 33, 59 Arithmetic calculations with constants, CLx, 18, 28 75, 177 $\left(\hat{x},r\right)$, 172 Arithmetic calculations, chain, \hat{y}, r , 172 20-22 Arithmetic calculations, simple, 19 C status indicator, 51 Arithmetic operations and the stack, Calendar functions, 29-31, 187 Calendar functions and the stack, Arithmetic, storage register, 24 175 Average. See Mean Cash flow diagram, 34-38 Average See Mean, 77 Cash flow sign convention, 33, 36 Cash flows, changing, 65 Cash flows, reviewing, 64 Cash flows, storing for I and L, 58, BEG . 37 65 BST, 92 Chain calculations, 20-22, 176-77 Backstep, 92 Clearing display, 18 Balloon payments, 40, 41 Clearing financial registers, 18 Battery, 193 Clearing operations, 17, 18 Battery power, low, 12, 16, 193 Clearing prefix keys, 17 Battery, installing, 193-94 Clearing program memory, 18, 89 BEGIN status indicator, 37 Clearing statistics registers, 18, 76 Bonds, 66-68, 163-67, 188, 202 Clearing storage registers, 18, 24, Bonds, 30/360 day basis, 163-65 Bonds, annual coupon, 166 Clearing X-register, 18 Bonds, corporate, 67 Compound growth, 37, 39

208

File name: hp 12c_user's guide_English_HDPMBF12E44

Printered Date: 2005/7/29

Page: 208 of 209

Dimension: 14.8 cm x 21 cm

Compound interest, 39–53, 186 Compound interest calculation, 11 Compounding periods, 34, 39 Conditional branching, 107–8 Conditional test instructions, 107 Constants, arithmetic calculations with, 177	Display format, mantissa, 73 Display format, standard, 71 Display formats, number, 71 Display, scientific notation, 72 Displaying numbers, 32 Displays, special, 73
Constants, arithmetic calculations	E
with, 75 Continuous compounding, 162, 191 Continuous effective rate, 162 Continuous memory, 70 Continuous memory, resetting of, 33, 37, 70, 72, 93, 94	EEX, 18 Editing a program, 113 Effective interest rate, converting, 161 Entry errors, 75 Error conditions, 74
D	Error, Pr, 74
DATE, 29–31 DB, 68, 172 ADYS, 51, 172 D.MY status indicator, 30	Errors, 74 Errors, in digit entry, 75 Excess depreciation, 148 Exponent, 18, 85 Exponential, 83
Data storage registers, 23–25	F
Date format, 29, 70 Dates, days between, 31 Dates, future or past, 30 Days, between dates, 31 Decimal places, rounding, 71 Decimal point, changing, 17 Declining-balance depreciation, 139 Deferred annuities, 134–35 Depreciation, 68, 136–48, 189–90	Factorial, 83 Financial registers, 32 Financial registers, clearing, 33 Fractional, 84 Future value, 36 Future value, calculating, 48 FV, 36
Depreciation, declining-balance,	G
139 Depreciation, excess, 148 Depreciation, partial year, 136–48 Depreciation, sum-of-the-years-digits, 141	GTO, 93
Depreciation, with crossover,	□, 12 □NT, 172
144–48 Digit entry, recovering from errors in, 75	IRR, 12 Indicators, status, 71
Digit entry, termination of, 19, 171	Instructions in program lines, 91
Discounted cashflow analysis, 57	Interest rate, annual, 43 Interest rate, periodic, 43

File name: hp 12c_user's guide_English_HDPMBF12E44 Printered Date: 2005/7/29

Display, 71

Page: 209 of 209

Dimension: $14.8 \text{ cm} \times 21 \text{ cm}$

Interest rate, periodic, 43

210 Subject Index

Interest, simple, 33
Internal rate of return, 57
Internal rate of return, calculating, 63
Internal rate of return, modified, 148
Interrupting a program, 97
IRR, 57, 148

K

Keyboard, 16

L

LSTX, 74
LAST X register, 70
Leasing, 151
Linear estimation, 80
Logarithm, 83
Looping, 103
Low-power indicator, 16

M

Mantissa, 18, 73
Mantissa Display Format, 73
Mean, 77
Mean, weighted, 81
memory, 23
Memory, program, 94
Modified internal rate of return, 148
Mortgage, price of, 126
Mortgage, yield of, 128
Multiple programs, 120

N

Negative numbers, 17
Net amount, 27
Net present value, 57
Net present value, calculating, 58
Nominal interest rate, converting, 160
Nominal rate, 162
NPV, 57

Number display formats, 71 Numbers, keying in, 17 Numbers, large, 18 Numbers, negative, 17 Numbers, recalling, 23 Numbers, storing, 23

0

Odd-period calculations, 50 Odd-period mode, 36 One-number functions, 83 One-variable statistics, 76 Overflow, 73

P

PSE . 97 PRICE, 172 Partial-year depreciation, 136 Payment, 36, 156 Payment amount, calculating, 46 Payment mode, 37 Payments, advance, 151, 156 Payments, number of, 39 Percent difference, 27 Percent of total, 28 Percentages, 26 PMT, 36 Populations, 79 Power function, 85 Pr error, 74 Prefix key, 16 Present value, 36 Present value, calculating, 44 PRGM status indicator, 88, 89 Program branching, 103 Program editing, 113 Program lines, displaying, 92 Program looping, 103 Program memory, 90, 94 Program mode, 88 Program, creating, 88 Program, interrupting, 97 Program, running, 89, 122

File name: hp 12c_user's guide_English_HDPMBF12E44

Printered Date: 2005/7/29

Page: 210 of 209

Dimension: 14.8 cm x 21 cm

Subject Index 211

Square Root, 83 Program, running one line at a time, Stack, 170 Standard deviation, 79 Program, stopping, 97, 101 Program, storing, 120 Statistics, 76 Status indicators, 71 Programming, 88 Programs, multiple, 120 Storage register arithmetic, 24 Storage registers, clearing, 24 PV, 36 Storing numbers, 32 R Storing programs, 120 Straight-line depreciation, 136 RND, 83 Sum-of-the-years-digits depreciation, Reciprocal, 83 registers, 23 Registers, financial, 32 Registers, statistics, 76 Two-variable statistics, 76 Renting versus Buying, 130 Residual, 156 U Round, 83 Rounding, 71 Underflow, 73 Running message, 12, 63 W S Weighted mean, 81 s, 172 SL, 172 X SOYD, 172 ^[X ≥ y], 74 STO, 23 Samples, 79 Savings, 160 YTM. 12 Scientific notation, 18, 72

File name: hp 12c_user's guide_English_HDPMBF12E44 Page: 2

Simple branching, 103 Simple interest, 33

Printered Date: 2005/7/29

Page: 211 of 209

Dimension: 14.8 cm x 21 cm

Yield, 154, 158