

Oddcast set up instructions

01-11-2010

- 1 Go to your feed page and click on the Technical Tab.
Scroll down to the section titled: Feed Technical Details (Advanced).
 - 2 Install Oddcast. Follow the normal prompts for the install.
After the install is complete, Oddcast should open on the desktop and start broadcasting.
 - 3 Uncheck AutoConnect for now so Oddcast does not start broadcasting.
 - 4 Under the Label "Encoder Settings", you will see what is your feed.
Right click on it to highlight it and select "Configure".
 - 5 From your feed page Technical Details (Advanced) as mentioned in #1, copy and paste the listed info from the feed page to Oddcast as follows:
 - Copy from Feed Page Server field and past to Oddcast Server IP field
 - Copy from Feed Page Mount field and past to Oddcast Mountpoint
 - Copy from Feed Page Password field and past to Oddcast Encoder Password field
 - 6 If doing a mono feed leave the Channels set at 1. If doing a stereo feed set Channels to 2. (Do not select Joint Stereo).
 - 7 Click OK.
 - 8 Under "Live Recording", select the correct sound card the radio is connected to.
 - 9 Click Auto connect and then click on Connect.
- You should see "Connected" under Transfer Rate.
Leave Oddcast up on your desk top to run.

Optional but suggested:

If you want your feed description to display in the players iTunes and Winamp, do the following:

- 1 Click on the "YP Settings" tab.
 - 2 In the Stream Name and the Stream Description fields, replace RadioReference.com with your feed description as listed on your feed.
Leave the other fields as is.
 - 3 Click OK
 - 4 Under "Live Recording", select the correct sound card the radio is connected to.
 - 5 Click Auto connect and then click on Connect.
- You should see "Connected" under Transfer Rate.
Leave Oddcast up on your desk top to run.
You will see the Oddcast icon on the desktop labeled: Online Scanner

To run multiple instances of Oddcast to run several feeds:

1 Go to your feed page and click on the Technical Tab.
Scroll down to the section titled: Feed Technical Details (Advanced).

2 Start to Install Oddcast.

At the Destination Folder page, you will see this: C:\Program Files (x86)\Online Scanner.
Add whatever you like at the end so this install is different from any other installs you make.

Examples:

- C:\Program Files (x86)\Online Scanner 1
- C:\Program Files (x86)\Online Scanner x (where x is feed name, mount or other. Keep it short)

Or

You can Change "Online Scanner" with your feed name.

Example:

- C:\Program Files (x86)\x (where x is feed name, mount or other. Keep it short)

3 Click install to complete the install.

After the install is complete, Oddcast should open on the desktop and start broadcasting.

4 Uncheck AutoConnect for now so Oddcast does not start broadcasting.

5 Change the name of the desktop icon to whatever you input in #2.

6 Then complete steps 3-9 under the first section: Oddcast set up instructions

7 Under "Live Recording", select the correct sound card the radio is connected to.
Each feed points to a separate sound card.

Repeat these steps for other instances of Oddcast you want to install.