

HO 224 83

CLOSED UNTIL

1994



Casualties from British WWII Blast Effects data as applied to nuclear war caused arguments with American disarmament activists. As this file shows, Britain took 10 psi peak overpressure as the 50% blast mortality rate for the population in houses, based on actual data, e.g. in the complete destruction of British houses within 77 feet from V1 "flying bombs" (Hitler's cruise missiles), mortality was 23.5% (Christopherson's RC-450, Table 8.2 on p145). This "confidential" data (used in 1972 DNA-EM-1 Table 10-1) agrees with "secret" American data from Hiroshima, but is much less than the 50% assumed in unclassified American reports.

CASUALTIES DUE TO IMMEDIATE EFFECTS OF GROUDBURSTS

People protected from heat flash in British houses

THIS DOCUMENT HAS BEEN
DOWNGRADED TO *Unclassified*
Authority in file No. *SAC 68 3/3/2*
Date *2/10/80* Initials *WAF*

PERCENTAGE CASUALTIES




Distance from GZ (Statute Miles)



HC 226/45

1467

CLOSED UNTIL



CD 92,02.

THIS DOCUMENT HAS BEEN
DOWNGRADED TO Unclassified
Authority in file No. SAG 68 3/3/2
Date 2-10-80 Initials mb

HOME OFFICE
C.S.A. RECORDS
No. A12/SA/RM/45

9

Confidential

/R & M 45

Home Office
Scientific Advisers' Branch

Casualty Rates for a Ground Burst 10 MT Bomb omitting
Residual Radiation - all in houses

Casualty rates for an air burst megaton weapon can be obtained by simple scaling up from kiloton weapons. For ground bursts the scaling is a little more complex and in this note comparable rates for a 10 MT groundburst bomb have been estimated.

Method of calculation

A 10 MT groundburst bomb gives a radius for A damage to houses of $3\frac{1}{2}$ miles, B damage 5 miles Cb damage 8 miles and Ca damage 13 miles.

Basic flying bomb data in REN 464

The death risk curve (X γ Fig 1) is derived from Fig 3 of Appendix 2 of C.D.J.P.S. (EA)(48)14 for secondary blast and debris casualties (houses - complete rescue). Since deaths in houses from secondary blast are related directly to the degree of damage of the house the distance scale has been expanded proportionately and the curve gives the corresponding version of deaths for secondary blast for a 10 MT groundburst bomb. There is also however a contribution of deaths due to gamma flash although this is distributed differently from that occurring with a kiloton explosion. The LD 50 in the open for a 10 MT bomb is 4,800 yards (= 2.7 miles) corresponding to $\frac{3}{4}$ mile for a nominal bomb. A dose of 10,000r in the open causes 30% deaths for people in houses. This dose would occur at 2,100 ft. from a nominal bomb or 2.2 miles from a 10 MT bomb. The point of mid-area range for A damaged houses is 2.45 miles and at this point 35% deaths would occur from debris and 19% from initial radiation making a total of 54%. This is therefore taken as the average fatal casualty rate for people in A damaged houses against a 10 MT groundburst bomb.

For people in B damaged houses initial gamma makes no appreciable contribution to deaths and so the secondary blast rate of 6% at the mid-area point is taken as the average figure. Curve $\gamma\gamma$ is the death risk curve for secondary blast and initial gamma combined.

The above figures are for immediate or inevitable delayed deaths. A proportion of people will be trapped and will die if not rescued. These people are classified as "alive but trapped" and they may be seriously injured, slightly injured or uninjured. In addition there will be people not trapped who are seriously injured or slightly injured or uninjured. The figures plotted in Fig. 1 for these categories were obtained by comparing Figs. 3 and 4 of Appendix 2 of C.D.J.P.S.(EA)(48)14 at the relevant points and adjusted to allow for the fact that the percentage deaths have been increased to include the initial gamma hazard.

Table I summarises the casualty rates obtained by the above means. It will be noted that very small percentages have been added for annuli in which casualties should not theoretically occur. These are purely adventitious figures added to give realism when the table is used for estimating casualties for exercises. Percentages have been worked out for Cb and Ca damaged areas separately but as this breakdown of the C damaged area is no longer officially recognised separate percentages are given also for the C area as a whole.

It must be emphasised that death and injury resulting from residual radiation, including fallout, are not included in these figures.

TABLE I

Percentage Blast Casualties (ignoring residual radiation) resulting from the ground burst of a 10 megaton weapon (All in houses)

Distance from G.Z. (miles)	Category of Damage	Killed	Alive but trapped			Untrapped	
			S.I.	L.I.	U.I.	S.I.	L.I.
0 - 3½	A	54%	11%	6%	16%	5%	4%
3½ - 5	B	6%	6%	6%	24%	7%	5%
5 - 13	C	0.2%*	0.6%	0.13%	0.13%	2%	1.7%
5 - 8	Cb	0.4%*	2%	0.5%	0.5%	6%	5%
8 - 13	Ca	0.1%*	-	-	-	0.5%*	0.5%

Remark
A)
AG)


* These are taken figures added for exercise purposes to give a few casualties beyond the range in which they would normally occur.

R & M 45

CONFIDENTIAL

FIGURE 1

PERCENTAGE CASUALTIES RESULTING FROM THE
EXPLOSION OF A 10 MT. GROUND BURST BOMB.
(ALL IN HOUSES — RESIDUAL RADIATION IGNORED)



S = Severe
L = Light
U = untrapped



HO 227/106

CLOSED UNTIL

1997

N
1467

HOME OFFICE

SA/PR 106

SCIENTIFIC ADVISER'S BRANCH

Distribution of basement fallout shelters by size

1. A pilot survey of communal fallout shelters was carried out in 1964/65. The shelters were the basements of communal buildings and the survey was carried out in the counties of Leicester, Hereford, in two London districts and four Scottish districts.

2. One of the purposes of the survey was to find how much of such shelter was available assuming that it would be occupied only by people in lightly built dwellings such as bungalows, prefabricated houses and caravans. In such dwellings it was considered that fallout protection would not be adequate nor could it be rendered adequate by improvised improvements. The amount available varied widely between districts, some having none and others more than was required. Details are given in a Scientific Adviser's Branch paper: SA/PR 94(Revised).

3. The working Party on Shelter Survival Requirements at its meeting on 5th April, 1966, considered among other things the possibilities of providing a medical package for use in communal shelters. It was pointed out that the make-up and size of such a shelter package or packages should depend to some extent on the number of shelter occupants. The data collected in the survey have therefore been reviewed to find the distribution of shelters by size.

4. Large numbers of shelters were found in Leicester and Hereford, other districts having very few shelters by comparison. As it was thought that there might be a significant difference in the size distribution between one area and another separate distributions were compiled for Leicester and Hereford and these are shown in the two upper histograms in the attached diagram.

5. It can be seen that the distributions are not very different from one another. Class intervals of 500 sq.ft. were used and the distributions are J-shaped the largest numbers of shelters having a floor area up to 500 sq.ft. However when the numbers in the first two classes are broken down into intervals of 100 sq.ft. it can be seen that there is a peak at between about 200 and 400 sq.ft.


6. As the distributions for Leicester and Hereford are not significantly different the data for both have been combined together with that for other districts to give a single distribution. It can be seen that about one half of all shelters found in the survey have areas between 100 and 500 sq.ft. and three quarters between 100 and 1000 sq.ft. Above 1000 sq.ft. the distribution has a very long tail, occasional shelters having areas as great as about 50,000 sq.ft.

7. The allowance of space per person, and consequently the number of people to be accommodated in a shelter, will probably vary according to circumstances. It seems likely that assuming no bunks in shelters the floor space should not be less than about 15 sq.ft per person.


D. T. Jones

April 1966.


DISTRIBUTION OF BASEMENT SHELTER BY FLOOR AREA



Note: 26 additional shelters between 10,000 and 66,000 Sq Ft



Note: 2 additional shelters at 17,000 Sq Ft



Note: 36 additional shelters between 10,000 and 66,000 Sq Ft



CD 807.

R.C. 450

~~CONFIDENTIAL~~

~~CONFIDENTIAL~~

RECORDS COPY

R.C. 450.

MINISTRY OF HOME SECURITY

MINISTRY OF WORKS
FRANCE THROUGH
No. A12A-RC-450

Scientific Adviser's Branch.

RESEARCH AND EXPERIMENTS DEPARTMENT

RECORDS COPY

ON REVIEW THIS DOCUMENT

HAS BEEN GRADED ~~CONFIDENTIAL~~

DATE .. 28/10/78. Initials .. LSH

Declassified 22.3.71
See note on fly-leaf
at front of this volume.

By George
Home Office Archives
28.5.75.

STRUCTURAL DEFENCE, 1945

by

D.G. CHRISTOPHERSON, D.Phil.

Fellow of Magdalene College, Cambridge.

Formerly of the Research and Experiments Department, Ministry of Home Security

January, 1946.

RECORDS COPY

Scientific Adviser's Branch.

R. C. 450

~~CONFIDENTIAL~~

MINISTRY OF HOME SECURITY

RESEARCH AND EXPERIMENTS DEPARTMENT

STRUCTURAL DEFENCE, 1945

by

D.G. CHRISTOPHERSON, D.Phil.

Fellow of Magdalene College, Cambridge.

Formerly of the Research and Experiments Department, Ministry of Home Security

-135-

- A damage - Completely demolished, less than 25% of external walls standing
- B damage - Partially demolished, at least 25% of external walls demolished
- C_b damage - Uninhabitable and too seriously damaged to be repaired in wartime
- C_a damage - Uninhabitable but capable of rapid repair
- D^a damage - Habitable but badly needing repair.

Table 8.2 then gives results comparable with those in Table 8.1.

TABLE 8.2

DAMAGE AND CASUALTIES FOR HOUSES

Grade of damage	Average circle radius (ft.)	No. of houses studied	Casualty data							
			No.	Total number of casualties			Total No. of occupants	Percentage of casualties		
				K	S/I	L/I		K	K + S/I	K + S/I + L/I
A	77	206	191	76	63	20	323	23.5	42.6	48.8
B	115	172	146	7	29	22	257	2.7	14.0	22.6
C _b	156*	299	282	0	30	19	326	0	9.2	15.0
C _a	-	173	158	0	4	4	182	0	2.2	4.4
D	-	44	43	0	0	0	45	0	0	0

* This value is an underestimate owing to the restriction of the zone of investigation to a distance of 170 ft. from the explosion. C_a and D radii were not measureable for the same reason.

	<u>Page</u>
<u>CHAPTER V</u>	
UNDERWATER EXPLOSIONS	
5.1 General account of the process of explosion under water	82-83
5.2 The initial underwater shockwave	83-85
5.3 Reflection of underwater shockwaves and its effect on damage; the "kinetic" wave	85-88
5.4 Underwater damage very close to the charge	88-90
REFERENCES	91
FIGURES 5.1 - 5.4	
<u>CHAPTER VI</u>	
92-101	
DIMENSIONAL THEORY AS APPLIED TO EXPLOSIONS	
6.1 Hopkinson's rules and their application	92
6.2 Basic dimensions of the relevant physical properties	92-95
6.3 Limitations of the theory of dimensions; "scale effect"	95-101
6.4 Appreciation of dimensional theory applied to explosives	101
REFERENCES	101
FIGURES 6.1 - 6.3	
<u>CHAPTER VII</u>	
102-124	
THE GENERAL THEORY OF THE BEHAVIOUR OF STRUCTURES UNDER SUDDENLY APPLIED LOADS	
7.1 The elastic system of one degree of freedom	102-103
7.2 The elastic system of many degrees of freedom	103-105
7.3 Application of the equivalent static pressure theory	105-106
7.4 Limitations of the elastic theory	106-107
7.5 Load deflection curves	107-111
7.6 General theory of the behaviour of "plastic" structures	111-118
7.7 Comparison with field and experimental results	118-122
7.8 Calculations for underground and underwater conditions	122
7.9 Empirical rules for earthshock damage to concrete walls	122-123
REFERENCES	124
FIGURES 7.1 - 7.14	
<u>CHAPTER VIII</u>	
125-151	
THE PROTECTION OF THE PUBLIC - SHELTERS	
8.1 General considerations in shelter provision	125
8.2 The concept of "vulnerable area"	125-128
8.3 Causation of casualties	128-131
8.4 Shelter occupancy	131-132
8.5 The main shelter types	132-146
8.6 The "calamity" risk	146
<u>APPENDIX</u>	
THE DISTRIBUTION OF EXPENDITURE	
	147-149
REFERENCES	
BIBLIOGRAPHY OF THE SHELTER PROBLEM	150-151
FIGURES 8.1 - 8.11	
<u>CHAPTER IX</u>	
152-167	
"BOMB-PROOF" SHELTERS AND FORTIFICATIONS	
9.1 The meaning of the words "bomb-proof" and "bomb-resisting"	152
9.2 Methods of attack - direct hit and near-miss	153-154
9.3 Contact explosions in air	154-156
9.4 The attack by shaped charges	156-157
9.5 Contact explosions in earth	157-158
9.6 The minimum thickness of floors	158
9.7 Geometrical considerations in design	158-159

CHAPTER VIII

THE PROTECTION OF THE PUBLIC:- SHELTERS

8.1 General considerations in shelter provision

The problem of the protection of the public from an attack can clearly be tackled from two directions:-

- (i) by removing people from areas subject to attack, and
- (ii) by providing them with accommodation within which they will be reasonably safe, even in an area which suffers heavy bombardment.

Obviously the first solution, when practicable, is much to be preferred. There is no doubt that thousands of lives were saved during the war by evacuation. But the solution has only a limited application. The work of the country must go on, and the workers must not only congregate in large numbers during working hours, but must also live relatively near their work, that is to say, in or near those areas which will attract attack. When the production of the country is concentrated, as is largely the case, in a few areas, the task of the attacker is rendered much easier, and in the colossal amalgam of industry, transport and commerce which is represented by a city like London, he can drop bombs almost at random knowing that few will be, from his point of view, entirely wasted.

The situation therefore arises in which people must be protected against an attack directed not primarily against them, but against the essential life of the country. The attempt may be made to destroy the actual means of production, the factories, by blast or fragmentation, to dislocate transport by blocking roads and railways by the craters of delay-fuzed bombs, or to force the workers to leave their work by destroying, usually by the use of fire, the dwellings in which they live. Against all these agencies of attack protection must be provided, and, if this is done, it will be found that to a very large extent, the people have also been protected against an attack, if one should be launched, directed primarily against them.

ANCE FROM BOMB (F.T.)

In estimating the relative efficiency of various shelter types, we take account of these considerations by introducing an "occupancy" factor. Suppose that the vulnerable area for a person taking shelter is V_s and for a person not taking shelter is V_n . Then if p per cent of the people for whom the shelter was intended do in fact occupy (on the average over a number of raids) the mean vulnerable area for these people is -

$$p V_s + (1 - p)V_n$$

and it is this quantity rather than the actual vulnerable area V_s of the shelter itself which should be regarded as giving the measure of efficiency.

The numerical value of the percentage occupancy p depends of course on many factors such as the weight of attack, the state of public morale, etc. We are here interested only in relative values as between different types of shelter. The figures given below, for example are estimates of occupancy during a typical night raid during the period 1940-41⁵:-

Type of shelter	Percentage of population occupying shelter
Interior (Morrison or protected room type)	75 - 80
Exterior domestic shelter (Anderson or domestic surface type)	50
Small public shelter (surface communal or trench type)	30

It may be that in these cases the figures will also cover fairly well raids of the short-duration day type. If, however, we included the large public shelter, such as the deep tunnel shelters in London, the occupancy figure would be very high for a night raid, but very low (owing to inaccessibility) when the time of warning was short.

(ii) The Anderson shelter (Fig. 8.1)

The Anderson shelter is, of course, simply a very small covered trench shelter in which the earth is retained by a corrugated steel arch held in place by light R.S. sections. Very large numbers of these shelters have been used in Great Britain and there is considerable experience of their behaviour. This experience indicates that, as expected, in a properly constructed and covered shelter few casualties occur except when the shelter itself is seriously damaged. If, for example, we categorize damage as follows:-

Category			
A1	Shelter totally destroyed	}	"heavily damaged"
A2	Shelter very badly distorted		
A3	End sheets removed, and/or moderate distortion of arch	}	"slightly damaged"
A4	Minor damage including reduction of earth cover		

We can relate the number of casualties occurring with the type of damage. This has been done for a group of 700 Anderson shelters which were attacked by flying bombs exploding within 170 ft. It is necessary to distinguish between those shelters which had (as all of them should have had) a baffle consisting of a brick wall or earth bank opposite the door to prevent the entrance of fragments or debris, and those in which the entrance was unprotected.

TABLE 8.1

DAMAGE AND CASUALTIES FOR ANDERSON SHELTERS⁶

Grade of damage	Average circle radius (ft.)	Number of shelters studied	Casualty data (Shelters with complete data)								
			No.	Total number of casualties			Total number of occupants	Percentage of casualties			
				Km	S/I ^m	L/I ^m		K	K + S/I	K+S/I+L/I	
All shelters -											
A1	15	13	13	5	1	0	6	83.3	100	100	
A2	24	14	12	3	6	2	19	15.8	47.4	58.0	
A3	39	24	15	2	6	6	28	7.1	28.6	50.0	
A4	66	71	57	1	5	5	71	1.4	8.5	15.5	
Shelters without baffles -											
A1	15	10	10	5	1	0	6	83.3	100	100	
A2	24	10	8	3	3	2	11	27.2	54.5	72.7	
A3	39	16	10	2	4	5	18	11.1	33.3	61.1	
A4	67	52	41	1	5	4	62	1.6	9.7	16.1	
Shelters with baffles -											
A1	15	3	3	0	0	0	0	-	-	-	
A2	24	4	4	0	3	0	8	0	37.5	37.5	
A3	39	8	5	0	2	1	10	0	20.0	30.0	
A4	72	19	16	0	0	1	9	0	0	11.1	

^mThe casualty classification is as follows:- K - killed. S/I - Seriously injured and detained in hospital. L/I - Slightly injured - received medical attention but not detained in hospital.

^mThe "average circle" radius is defined as the distance such that the number of shelters undamaged within a circle of this radius is equal to the number damaged outside the circle. It corresponds closely to the "vulnerable area" but is easier to compute.

The vulnerable area, as defined in equation (8.1) can be readily computed from these results, if we replace the integral in that equation by an arithmetic summation of the areas of damage times the probability of injury in each area. Fixing attention on the totals of killed and seriously injured we find the following figures -

Vulnerable area K + S/I

All shelters	2,830 sq.ft.
Shelters without baffles only	3,200 sq.ft.
Shelters with baffles only	1,720 sq.ft.

- A damage - Completely demolished, less than 25% of external walls standing
- B damage - Partially demolished, at least 25% of external walls demolished
- C_b damage - Uninhabitable and too seriously damaged to be repaired in wartime
- C_a damage - Uninhabitable but capable of rapid repair
- D damage - Habitable but badly needing repair.

Table 8.2 then gives results comparable with those in Table 8.1.

TABLE 8.2

DAMAGE AND CASUALTIES FOR HOUSES

Grade of damage	Average circle radius (ft.)	No. of houses studied	Casualty data							
			No.	Total number of casualties			Total No. of occupants	Percentage of casualties		
				K	S/I	L/I		K	K + S/I	K + S/I + L/I
A	77	206	191	76	63	20	323	23.5	42.6	48.8
B	115	172	146	7	29	22	257	2.7	14.0	22.6
C _b	156*	299	282	0	30	19	326	0	9.2	15.0
C _a	-	173	158	0	4	4	182	0	2.2	4.4
D	-	44	43	0	0	0	45	0	0	0

* This value is an underestimate owing to the restriction of the zone of investigation to a distance of 170 ft. from the explosion. C_a and D radii were not measureable for the same reason.

Following the same procedure as before, we find, for killed and seriously injured taken together, the vulnerable area about 16,000 sq.ft. or more than nine times that for the properly protected Anderson shelter.

The flying bomb was of course a blast weapon, i.e. it always exploded on the surface without penetration. As such, it was equivalent to an H.C. bomb of charge-weight ratio 75 per cent and charge-weight (RDX/TNT) about 1,050 lb. and accordingly we may estimate the vulnerable area of the properly protected Anderson shelter as no more than 2,750 sq.ft. per ton of bombs of this type. But, as we remarked when considering trenches in general, any sub-surface shelter cannot readily be attacked by blast weapons; the main threat is from the delay-fuzed penetrating bomb.

Direct evidence as to the casualties produced by such bombs in Anderson shelters is scanty, due partly to the difficulty of identifying the bombs responsible for specific incidents in raids in which several sizes of bomb variously fuzed were used simultaneously, and partly to the fact that in the early part of the war the system for the collection of the required information was not fully developed, while more recently, the penetrating bomb has more and more been superseded by blast weapons. It is possible, however, to relate damage to the shelter directly with the crater size of the bomb causing the damage, and some results obtained in this way are shown in Fig. 8.2. From this diagram we can see that the vulnerable area for "heavy damage" from penetrating bombs is about 1.6 times the crater area. The average crater area for (say 50 kg. bombs fuzed 1/40 sec. delay or longer is about 180 sq.ft. (weighting the areas for various types of soil in the proportions in which they have in fact occurred); so that we may estimate the vulnerable area (killed or seriously injured) as approximately 290 sq.ft. for this type of bomb, giving the vulnerable area per ton 5,800 sq.ft.

* In Reference 7 Professor S. Zuckerman found that the vulnerable area for the occupants of a group of small shelters (mostly Andersons) was only 270 sq.ft. but some of his data may have involved non-penetrating bombs. In the same paper, he shows that the corresponding figure for people in houses is 1,430 sq.ft. about 5-6 times as great. In a later paper R.E.N.182 "A comparison of the number of casualties caused by German bombs of different sizes", Professor Zuckerman found that the vulnerable area against the 50 kg. for persons in Anderson shelters was no more than 126 sq.ft. compared with 810 sq.ft. for persons in houses. Note that although these figures are much reduced, no doubt as a consequence of the increased use of instantaneous fuzes in the raids studied, the ratio between the two remains about the same as before.

Fig. 8.2 not reproduced.

Other larger types of trench shelter will clearly be more vulnerable due to the increased risk of a direct hit, and to the fact that many of the lining materials used were less capable of distortion without rupture than the corrugated steel of the Anderson.

(iii) The surface shelter (Figs. 8.3 and 8.4)

The public surface shelter as originally designed was intended for use in streets, factories, etc., where trenches were not appropriate, due to the unfavourable nature of the ground or other causes. It was thought before the war that the main risk to be contended was that from fragmentation, and the prime requirement was therefore to make the walls fragment-proof. In fact, the principal risk arises from the collapse of a shelter as a result of blast or earthshock, and if these risks are adequately met, the fragmentation risk will be negligible.

The standard of protection aimed at was also much lower than that subsequently achieved. The earliest surface shelters were designed to be proof against blast and fragmentation from a 500 lb. bomb (TNT filled) at 50 ft. and so they were. But it was afterwards found to be possible to reduce this distance to 15 ft. i.e. to nearly the standard of protection afforded by the Anderson shelter. Owing to its larger plan area, it was necessary for the surface shelter to be proof against a near-miss even closer than that required to damage an Anderson, in order to give a comparable degree of protection.

At this distance the shelter had to be proof -

- (a) against the blast and fragmentation from a surface burst-bomb;
- (b) against the earthshock from a delay-fuzed bomb, and in addition,
- (c) the velocity with which it was displaced by earthshock had to be below the critical velocity for injury laid down in paragraph 8.3.

We have already in Chapter VII discussed in detail the problem of the design of wall panels against blast. A shelter wall does not of course differ from any other in this respect so it is not necessary to recapitulate the calculations given in that chapter.

The conclusion reached is that walls of thickness $13\frac{1}{2}$ in. for brick or 12 in. for concrete reinforced in each case against earthshock in the manner shown in Figs. 8.3 and 8.4 are satisfactory from the point of blast. It is also obvious that the performance will be improved if the shelter is allowed to slide freely on its foundation, thus absorbing some part of the blast energy. We have also noted that these walls are virtually proof against fragmentation.

We must, however, contemplate a form of failure which has not been covered by the fundamental investigations in the earlier chapters - the risk that the shelter may disintegrate either as a result of the original earthshock or more probably as a result of the impact which occurs when the shelter strikes the ground again after being projected through the air.

The earlier unreinforced surface shelters were particularly liable to collapse in this way, and a large part of the full-scale experimental work carried out by R. & E. Department in the early part of the war was directed towards determining a design which would not collapse under severe earthshock conditions, and also to devising means whereby the original unreinforced types could be strengthened up to the required standard.

A considerable number of full-scale tests were carried out with this end in view, a typical layout being that shown in Fig. 8.5. The designers were, of course, throughout handicapped by the necessity for extreme economy in the use of steel, which was, at that time, in very short supply, and in considering the designs which are shown as Fig. 8.3 and Fig. 8.4 it must be remembered that these forms were considered the best that could be done with the amount of steel available.

The technique of design for these conditions had to a great extent to be improvised. The remarks made in chapter VII with regard to the treatment of a "one-life" structure, and with regard to the consideration of ultimate strength rather than elastic limit, of course holds good in this context. But it is not immediately apparent how estimates can be made of the forces disintegrating the shelter, and thus of the strength necessary to hold it together. A means of approach to this problem of the measurement of the disintegrating forces was found in cine-photography. A series of photographs were taken at a moderately high speed (say 200 frames per second), of the process of disintegration of an unreinforced shelter under the specified conditions. The velocities with which the various parts scattered could then be measured from the film, and hence an estimate of the disintegrating impulses could be obtained.

One such photograph shown in Fig. 8.5a illustrates the way in which an ordinary rectangular brick shelter with reinforced concrete slab roof and floor breaks up and is demolished by a 500 lb. bomb buried 12 ft. 6 in. at 15 ft. from the shelter wall horizontally*. This photograph and others like it illustrate clearly enough what the task of the designer is -

- (a) the separation of floor, roof and walls, as a result of "knock-on" effect must be prevented,
- (b) the shelter must not be allowed to "fold up", i.e. to assume the form of an elongated parallelogram.

It is found that the forces necessary to prevent the separation of the various elements of the shelter are not large. A very small percentage of steel reinforcement (as little as 0.06 per cent by volume has been used), if carried continuously from the floor through the walls and into the roof, is sufficient to keep the whole structure together. When a very low percentage reinforcement is used, however, it is usual to provide cross-walls at intervals along the shelter length, as shown in Fig. 8.4, with a view to stiffening the section, and preventing "folding up". The floor, which was omitted in some of the earlier types, is almost a necessity for the same reason. Photograph 8.7, taken under the same conditions as 8.5a, illustrates the success of these measures.

The comparatively low percentage reinforcement necessary to keep the shelter together can be easily demonstrated by a calculation as follows:-

Suppose that an unreinforced shelter is tested under the specified conditions, and the maximum relative velocity of roof and walls is measured photographically and found to be 5 ft./sec. in a shelter of area 30 ft. x 8 ft. having walls 1 ft thick⁸. Then the kinetic energy of the roof, assumed 5 in. thick, and of density 144 lb./cu.ft. is

$$\frac{60 \times 25}{64} \text{ ft. lb./sq.ft.}$$

In this plan there are 72 ft. of wall supporting an area 240 sq.ft., so that the kinetic energy of the roof per foot run of wall is -

$$\frac{60 \times 25 \times 240}{64 \times 72} \text{ ft.lb.}$$

The work done in extending the reinforcement is necessarily less than this, since much of the energy will go into elastic vibrations of the roof, etc. Then, if there are A sq.in. of reinforcing bars per foot run of wall, having yield stress 50,000 lb./sq.in. the extension of the reinforcement

* In the actual tests 250 kg. (550 lb.) German S.C. bombs were used.

is necessarily less than δ ft. given by -

$$A \delta 50,000 = \frac{60 \times 25 \times 240}{64 \times 72}$$

For 0.06 per cent reinforcement in a 1 ft. thick wall $A = 0.06 \times 1.44$ so -

$$= \frac{60 \times 25 \times 240}{64 \times 72 \times 50,000 \times 0.06 \times 1.44} \text{ ft.} = .22 \text{ in. (approx.)}$$

The separation of roof and wall cannot therefore be more than $\frac{1}{4}$ in. and will probably be much less. In practice it is quite probable that not even a crack would appear there.

This calculation is an example of the use that can be made in design on the one hand of structures which are specifically intended to fail, and, in failing, to give information about the forces causing failure, and on the other hand of the cinematographic technique of velocity measurement, which has been widely used in many connexions and which, as applied to the problem of earthshock movements and velocities, requires only relatively simple equipment. The photographic method also, of course, gives the information necessary to ensure that requirement (c) is met, - that the velocities imparted to personnel in the shelter are not such as to cause injury, regardless of whether the shelter is damaged or not. Walley's paper⁸ indicates that the velocities imparted to the shelters are lower than the threshold injurious velocities quoted in paragraph 8.3, but not by much. Clearly it is useless to endeavour to strengthen the shelter further with a view to ensuring that it successfully resists demolition under even more severe conditions, unless at the same time we make it much heavier, so as to prevent the velocity of projection rising above this threshold value. We shall have occasion to consider this point in more detail, when we come to the consideration of "bomb-resisting shelters" (Chapter IX).

One further possibility must be taken into account; the surface shelter must necessarily be capable of supporting a considerable mass of debris on its roof. Moreover, since it is commonly constructed on roads and among buildings, it must be capable of sustaining the impact of heavy masses of masonry, or perhaps large pieces of concrete projected into the roof at moderate velocities. In Chapter IV we have stated that the velocities likely to be achieved by such large missiles as a result of the explosion of a buried bomb are not likely to exceed about 70 ft./sec.

Not much experimental work is available as to the effects of the impact of relatively slow moving missiles on concrete slabs⁹. All the work quoted in Chapter VII on impact on concrete beams refers to "beams" which were supported at the ends only and failed by simple fracture at the centre. The problem of the slab which under some conditions will fail by "punching" is essentially different. In R.C. 188, however, Gimpel and Marshall reported a valuable series of experiments, although their slabs, being reinforced with expanded metal, were not typical of shelter roof design. The slabs tested were all similar of 3 ft. square and $2\frac{1}{2}$ in. thick, simply supported on a free span of 2 ft. 6 in. with 0.7 per cent reinforcement, and having an ultimate static strength under a central load of about 3 tons. A weight of 7.9 lb. was dropped from various heights on this slab, and it was found the energy required to hole the slab, when the load was distributed over an area 3 in. square was in excess of 200 ft./lb. When a cast iron ball was used as striker so that the area loaded was smaller, the energy required was about half as much. The damage caused was quite local, suggesting that for impacts at moderate velocity the method of support of the slab is not a matter of the first importance.

⁹ If the bomb explodes immediately below the road surface the velocities will be much higher, but the concrete will be broken up into much smaller pieces.

Applying the dimensional theory outlined in Chapter VI we find that a rigid mass of 63 lb. falling with velocity 40 ft./sec. on to a slab 5 in. thick, similarly reinforced, would just fail to hole it, provided that the area of contact was not less than 6 in. square. In the rough and ready demolitions carried out at the end of the war, a weight of 22 cwt. was dropped 4-5 ft. on to such roofs, and only succeeded in making a hole by repeated impacts on the same point. On this basis it may therefore be expected that the occasions on which shelter roofs of the type shown in Figs. 8.3 and 4, will be holed by debris will be very rare. Experience has confirmed this conclusion. Of shelters built experimentally on concrete roads with reinforced concrete roofs 5-6 in. thick only one was holed by debris in a test under the specified conditions. Cases in which shelter roofs have been holed by debris in actual raids are so rare as to be almost non-existent.

All the causes of injury enumerated in paragraph 8.3 have now been considered, except (d) fragmentation injury and (f) direct blast injury.

In Chapter III we pointed out that walls of the thickness shown in Figs. 8.3 and 8.4 would seldom, if ever, be penetrated by fragments from bombs bursting outside. At the standard 15 ft. distance from the 500 lb. bomb, we showed in Chapter III that the "mass fragmentation" effect would powerfully reinforce the blast effect, but in Chapter VII we argued that these walls would be adequate to resist both acting together. The risk from fragments entering by way of doorways, must of course be combated by providing a suitable "baffle" wall, covering the entrance (or possibly, a suitable fragment-proof door). The complexity of the baffling necessary will vary according to the design of shelter used, but in general it should be such that no fragment can enter the inhabited part of the shelter without at least one ricochet.

A direct measure of the vulnerability of the normal brick surface shelters is not easy since no one standard design was built in large numbers. The shelters actually used were for the most part strengthened versions of the original unreinforced brickshelter, and a number of different systems of strengthening were employed. For example, the exterior of the shelter might be covered by a steel mesh, held in position by an additional $4\frac{1}{2}$ in. brick skin, and by additional concrete on the roof. Alternatively, a similar plan could be adopted in the interior (Fig. 8.7) but in so doing the shelter was rendered considerably safer than the reinforced type designed ab initio as in Figs. 8.3 and 8.4. The walls were 18 in. thick as opposed to $13\frac{1}{2}$ in. thick in the reinforced design, and the roof is also thicker. These increases in weight will improve the performance substantially both against blast and probably also against earthshock.

The evidence of field results is that such a strengthened shelter will not be damaged seriously by blast from a flying bomb at distances greater than about 35 ft. This test is almost certainly appreciably more severe than that imposed by the 250 kg. S.C. bomb (filled TNT) at 15 ft. and accordingly the shelter is somewhat safer than the standard laid down. The reinforced brick shelter Fig. 8.3 is probably only just up to the required standard, although the reinforced concrete is also slightly better. The vulnerable area for the strengthened type could not be estimated with any degree of confidence from the comparatively small amount of field data available, but what there is suggests a value of about 2,700 sq.ft. against the flying bomb. When attacked by a blast weapon the shelter is thus markedly inferior to the Anderson type. When the attack is by penetrating bombs, however, there is little difference between the two.

The public surface shelter is, however, particularly vulnerable to one form of attack which has not materialized in an acute form in this war. There would be no difficulty about designing a bomb of weight about 10-15 lb., charge-weight perhaps 2-3 lb., which would be capable of penetrating the roof of thickness 8 in. or less and exploding inside. The casualties from the internal explosion of such a bomb would be heavy, and even allowing for the fact that owing to fuze defects some bombs would detonate either before penetrating the roof or after passing the floor, the average vulnerable area is likely to be perhaps 100 sq. ft. or more. The vulnerable area per ton aircraft load is then

about 20,000 sq.ft. - more than four times that for the large blast weapon. Such a weapon will be relatively less effective against the smaller shelter types, such as the Anderson, owing to the small area which they present to direct hits.

In addition to the public surface shelters, illustrated in Figs. 8.3 and 8.4 several other types of brick surface shelter were in use. The small domestic type of shelter illustrated in Fig. 8.8 were intended to replace the Anderson shelter when the ground was unsuitable for subsurface construction. Some of the earlier types had arched or corbelled roofs, with a view to economy in steel, but this construction has obvious weaknesses under earthshock, and the usual flat roofs tied by reinforcing to the walls are much to be preferred.

The "communal" type illustrated in Fig. 8.9 consisted in effect of an amalgam of small "domestic" shelters constructed together. The weight of the whole was naturally greater than that of the less heavily partitioned public shelter, and for this reason it was probably slightly safer, particularly against the "small bomb" attack envisaged above. In general, however, all these surface brick shelters, when strengthened up to the 1941 standard could be considered to provide approximately comparable protection.

(iv) The "indoor" shelters

The use of strengthened basements or other strengthened rooms as shelters was widespread early in the war. Provided that the buildings chosen for this purpose were suitable, and that the strengthening was adequate, these shelters afforded a fair measure of security, particularly against blast weapons. In general the requirements were:-

- (1) the strutting should be such that the roof was capable of supporting the entire debris load of the building above if it completely collapsed, and moreover should have enough lateral stability to eliminate the possibility of collapse when the roof was loaded unsymmetrically by the collapse of one part only of the building.
- (2) The strutting should be so placed that, in the event of the destruction of one or more walls of the shelters by earthshock from a near-miss, it would not be damaged to an extent which would render it incapable of supporting the debris load resulting from the collapse of upper floors. This could be done by placing the main struts at some distance from the exterior walls - never against them. Other minor modifications, such as the bricking up of area lights, etc., were also made, and where the shelter was large in area, it was subdivided by partition walls comparable in strength with surface shelter walls in order to reduce the lethal area of a bomb of medium calibre penetrating into the shelter.

The degree of protection afforded by such a shelter was to a very large extent governed by the nature of the building in which the shelter was placed. In a modern steel-framed building the risk in a basement shelter was very small - probably not more than 1/10th as great as that in the Anderson, if the improved occupancy is allowed for, and by bricking up windows, etc., an equally good shelter could be constructed on the second or third storey of such a building.* Moreover, the weight of debris falling on the roof of the shelter consisting, in a framed building simply of demolished partition walls, etc., can usually be easily carried by the frame without additional strutting, provided that the roof of the shelter is sufficiently substantial to prevent local collapse. Much the same is true, though the risks were slightly greater, in a reinforced concrete framed building. In any future plan for the protection of the public the utilization of such buildings, which are likely to be more numerous in the future than they have been in the past, may be a prime consideration.

* For a discussion of steel and reinforced concrete framed buildings cf. Chapter X.

In multi-storey load-bearing buildings of the "monumental" type protection is fairly good particularly against bombs of small or moderate calibre. When the attack is by large bombs serious calamities are likely to occur. The weight of debris falling on a shelter if a large part of the building above is demolished is very great, and the time taken to extract the occupants of the shelter if they have survived, is proportionately long. Although such shelters may be of value in providing "quick" protection for persons working in these buildings they cannot be regarded as satisfactory as a standard type of public shelter.

At the other end of the scale we come to the problem of the provision of a suitable indoor shelter which could be used in the millions of small two-storey houses, terraced, detached or semi-detached, which exist in the country. Few of these houses have cellars or basements and even where these exist, they do not provide any satisfactory protection since the occupants cannot be situated very far from the external walls, and these are as liable to collapse by earthshock as a trench shelter constructed of a non-ductile material. Such a collapse of an external wall is likely to cause injuries at close quarters even if strutting prevents the collapse of the house as a whole.

On the other hand, it was clear by the end of 1940 that an indoor shelter for the small house was urgently desirable. The occupancy statistics (paragraph 8.4) alone argued strongly in its favour, and indeed the idea had been mooted at a much earlier date. The objections which were then foreseen were as follows:-

(a) the shelter could not be such as would decrease substantially the living accommodation in the house, which was, as a rule, already fully utilized. This objection was fatal to most plans for "strutted rooms", etc;

(b) the shelter must be capable of sustaining the debris load resulting from the complete collapse of the house; but access to it, - and escape from it - must be as easy as possible. It was greatly feared that if persons were trapped in such shelters the onset of fire would put an end to the usefulness of the shelter.

It was to meet these objections that the well-known "Morrison" table shelter was introduced; and since this shelter has been, on the whole, the most successful in practice in this war, we shall devote some attention to it.

(v) The Morrison table shelter

Fig. 8.10 shows the design adopted. The details were to some extent determined by the material which happened to be available for the purpose at the time.

The plan area 6 ft. x $4\frac{1}{2}$ ft., while giving adequate room for 2 persons to sleep (4-5 persons were accommodated in a "2-tier" shelter) was not much larger than that of the ordinary table which the shelter was intended to replace. The steel-mesh curtains forming the sides could readily be removed and provided means of access from any direction. It was found that the fears of the pre-war advisers on the subject of fire in debris were not justified. Where a house was so completely demolished that the occupants of the Morrison were left with no route of escape the lack of air supply at all points, except those exposed on the surface of the heap of debris, combined no doubt with the quantity of stone dust suspended in the atmosphere, made it almost impossible for fire to maintain itself in the ruin. Indeed, such demolished houses acted as effective fire-breaks in incendiary raids. True, houses which were only partially demolished or severely damaged were particularly susceptible to fire; but in such houses the occupants of a Morrison usually had at least one route of escape open.

It may be that in the extremely intense fire "tempests" caused by the heavy R.A.F. raids against German cities late in the war, this would no longer have been true. It has been stated that in the heavily built up zone in the centre of a city, when almost every building was on fire, escape by way of the streets became impossible, and casualties due to fire among persons in otherwise undamaged shelters were very high. This, of course, suggests that any type of shelters should be built in an open space and not among a concentration of inflammable buildings. Under the conditions in which the Morrison shelter was most widely used, however, in small houses in areas where the building density was comparatively low, it may be that no fire tempest so severe as to prevent escape from the affected area could have been induced.

The height of the shelter was made low enough to be below window sill level in the average room, and the position in which the shelter was placed was selected to be as far as possible out of range of flying glass. By the methods of Chapter III we can predict that ordinary 9 in. brick walls of a two-storey house were very nearly proof against fragmentation, especially from the higher charge-weight ratio weapons, and that even a $4\frac{1}{2}$ in. brick partition offers a substantial measure of protection.

The main structural requirements were laid down from a detailed consideration of the loads which would be applied to the shelter when the house containing it was demolished.

The shelter had to be capable of sustaining -

- (1) A dead load of 320 lb./sq. ft. laid over the whole area of its "roof" or top.
- (2) The weight of an area of floor 14 ft. x 6 ft. 6 in. x 20 lb./sq.ft. (the maximum floor area which can strike the shelter when placed in a room in which the supported span is 14 ft.), i.e. the total of the dead load and superimposed load on timber floors of normal domestic occupancy, falling flat on the shelter from a height of 6 ft.
- (3) The same area of floor, loaded similarly, hinged about one wall, and falling from the same height to strike the edge of the shelter in an oblique direction.
- (4) A horizontal load 160 lb./sq.ft. applied on any side (to resist the horizontal thrust from the debris in a collapsed house).

A full discussion of the design of a shelter to meet these specifications will be found in R.C. 204 "The design and testing of the table (Morrison) indoor shelter". The procedure may be summarized as follows:-

- (a) The frame is designed in accordance with the procedure of Chapter VII so that the members are capable of absorbing in plastic bending without excessive displacement the energy imparted to them by the impacts described.
- (b) The other parts, e.g. the top plate and the side weld-mesh curtains, and the bottom "mattress" are designed to develop the full strength of the frame.

Actually, the 22 gauge (.03125") plate would be sufficient for the purpose, but in fact a $\frac{1}{8}$ in. steel was used since a supply of the thicker plate was more readily available. It was the original intention to secure the steel laths of the mattress by bending over the bottom angles and securing to the side panel studs. In order to facilitate bundling of the laths for transport this plan was abandoned in favour of attachment by hooks and springs. Experience, however, showed that although the latter plan was reasonably satisfactory, the mattress was inclined to break away from the frame under severe conditions, and it might have been worth while to retain the original design.

The various designs evolved by R. & E. Department, together with a number submitted for consideration by independent designers, were tested "ad hoc" under the conditions described above. Fig. 8.11 shows a test being carried out under conditions (3). Small deformations of the shelter under tests (2) and (3) were considered acceptable, provided they were not so large that the occupants would have been endangered. In the actual tests, the rectangular block of masonry of weight 336 lb. dropped centrally on the shelter was substituted for the floor described in (2) and constituted on the whole a more severe test.

The only risk which remains to be considered is that arising from the shelter and the occupants being thrown about by blast or earthshock. This risk can never be entirely eliminated, particularly in a light shelter; but the Morrison design aimed to reduce it in several ways.

In the first place, the shelter was always provided with a floor of interwoven steel strips, which ensured that if the shelter was lifted, the occupants went with it. Without this floor there would be a serious risk that the occupants would be injured by quite a small displacement of the shelter. Secondly, the mesh sides ensured that there would always be very complete and rapid diffraction of blast inside and outside the shelter, so that no large velocity would be imparted to it by blast. Finally, the horizontal ties at floor level, in addition to contributing greatly to the stiffness and stability of the shelter, went far to ensure that the "legs" of the table would not be driven through the floor on which the shelter stood, with resulting crushing of the occupants between floor and roof.

Turning now to direct field experience of the behaviour of Morrison shelters, we find that, as far as delay-fuzed penetrating weapons are concerned, this is almost entirely lacking, since the shelter did not come into common use until the period (after the middle of 1941) when the enemy confined himself almost entirely to blast weapons. We have however some reliable information, again collected during the flying bomb attack. We can relate the four variables -

- (i) casualties to occupants
- (ii) damage to shelter
- (iii) damage to house in which shelter was placed
- (iv) distance from bomb

For this purpose we can define the following categories of shelter damage:-

- M1 Shelter destroyed (minimum distance between mattress and top reduced to less than 12 in. as a result of buckling of the top plate, or distortion of the frame)
- M2 Heavy damage (minimum clearance between mattress and top more than 12 in. but maximum deflection of top more than 9 in.)
- M3 Slight damage (deflections less than 9 in.)

Table 8.3 gives the relation between the type of damage suffered by the shelter and the condition of the house (classified as notes to Table 8.2) in which the shelter was placed.

TABLE 8.3

FATE OF MORRISON SHELTERS IN DAMAGED HOUSES

Category of house damage	Number of shelters damaged to the category					
	Total	M1	M2	M3	Undamaged	Unknown †
A	53	1	1	11	26	14
B	48	0	0	2	46	0
C _b	61	0	0	0	61	0

† If the shelter was not occupied, information about its behaviour was sometimes unobtainable.

It will be seen that out of 39 shelters of known behaviour exposed in houses which were to all intents and purposes totally demolished, only two were seriously damaged, while of 109 shelters in houses seriously damaged, all survived.

This extremely small number of shelters heavily damaged makes it impossible to determine from practical experience what is likely to happen to the occupants of such shelters. Of the five occupants of the two shelters referred to above, only one was injured. Table 8.4 below corresponds in all particulars to Table 8.1 for the Anderson shelter.

TABLE 8.4

DAMAGE AND CASUALTIES FOR MORRISON SHELTERS

Grade of damage	Average circle radius (ft.)	No. of shelters studied	Casualty data									
			Shelters with complete data						Total No. of occupants	Percentage of casualties		
			Number	Total number of casualties			K	K + S/I		K + S/I + L/I		
				K	S/I	L/I						
M1	-	1	1	0	0	0	2	-	-	-		
M2	-	1	1	0	1	0	3	-	-	-		
M3	51	13	12	1	4	4	29	3.4	17.2	31.4		

The best that can be done with these rather fragmentary results is to group all the damaged shelters together. We can then find that for persons in Morrison shelters within 51 ft. of the point of burst the proportion of casualties will be as follows:-

<u>No. exposed to risk</u>	<u>No. killed</u>	<u>K + S/I</u>	<u>K + S/I + L/I</u>
34	1	6	10
100%	3%	17.6%	29.4%

The persons further away from the burst are practically safe. The vulnerable area for killed and seriously injured which results, is 1,440 sq. ft. - an even lower figure than that already quoted for the Anderson shelter.

It will be realised, of course, that the more effective a shelter is the less reliable will be the numerical information relating to its performance. As the number of casualties occurring in the shelter decreases, the variations in the number due to chance factors necessarily form a large proportion of the whole. On the other hand, as we noted earlier in this chapter, it would be a cardinal error to attempt to increase the number by investigating, for the purpose of vulnerable area determination, only those incidents in which casualties had occurred. All incidents in which the shelter is "exposed to risk" under the assigned conditions must be investigated, or, at any rate, if a selection is made, the basis of it must be quite arbitrary, and must not be related in any way to the performance of the shelter.

Although, for the reason given above, we have no direct information as to the effect of penetrating bombs against the Morrison shelter we may anticipate that the vulnerable area per ton of bombs will not be greater and may well be less than was the case with the blast weapon. The house damage per ton of bombs, will certainly be less, for example, from 4-250 kg. S.C. or 2-500 kg. S.C. delay-fuzed than from a 1-ton blast bomb, and accordingly we may expect some reduction in the vulnerable area for Morrison shelters.

The small 10-15 lb. bomb, which is a menace to the surface shelter, is also dangerous here. Such a bomb, exploding in the same room as the Morrison would certainly expose the occupants to a severe risk. But the problem of fuzing such a bomb to explode between (say) 15 ft. and 25 ft. below a roof of variable weight, after passing through an upper floor containing a variable amount of furniture of variable resistance, would be very difficult, and it would not be surprising if not more than 1/5 of all bombs striking on the required area exploded at the right level. If, as may well be the case, even these bombs kill or seriously injure only half the shelter occupants the vulnerable area per ton will be found to be no more than that for the large blast weapon.

On the whole, therefore, the Morrison shelter can be regarded as the best (though not incomparably the best) solution to the problem of the shelter of the occupant of the small house. This is especially true when "occupancy" figure is taken in to account. It is probable that the shelter could also be used in the lighter types of three-storey buildings, though the time of rescue of the occupants, in cases where the shelter is buried, is likely to increase sharply with the weight of debris covering it.

(vi) Tunnel shelters

The physical data on which the design of tunnel shelters must be based has already been given in earlier chapters. In Chapter II we described the propagation of blast in tunnels, and in Chapter IV we gave the conditions under which spalling or collapse of the tunnelled rock could be expected. All that is necessary here is to refer to the question of vulnerable area.

We must here differentiate sharply between the effect when the bomb explodes in or very nearly in the tunnel, and the effect when it is sufficiently far away to cause nothing more than spalling of the rock. In the latter case, a local block may occur; but provided that the shelter is furnished with an adequate number of exits so that no large number of people can be trapped by a single fall, casualties will only occur in the limited area in which the fall has taken place. On the other hand, when the bomb penetrates into the tunnel casualties are likely to be numerous, not so much as a result of direct blast effects, as in consequence of the very large "windage" effects which will cause injury both as a result of people being violently displaced themselves, and as a result of the violent displacement of loose material of all kinds. It is therefore essential that in a tunnel shelter which is at a depth at which there is even the barest possibility of penetration, the shelter should be intersected either by numerous blast traps of the kind described in paragraph 2.7 or by extremely strong and heavy blast walls, or both, the number of persons within any one subdivision being strictly limited.

Tunnel shelters have not been used much in the United Kingdom (with the exception of the London tube railways, to which we shall refer again in Chapter XIII), and for an example of a tunnel system in practice, we must return to the German constructed V-weapon sites in the Pas de Calais mentioned in Chapter IV. As we stated, a tunnel system for which the overhead cover above the crown of the tunnel arch was 95 ft., was attacked by 12,000 lb. M.C. bombs fuzed a delay long enough to ensure that the bomb came to rest before exploding. Actual casualty figures for this attack are not available, but if we assume that all persons in the portions of the tunnel completely blocked or very heavily spalled by debris were casualties, we find a vulnerable area of 6,750 sq.ft. per bomb, or 1,260 sq.ft. per ton aircraft load. One of the bombs however "blew through" into the tunnels which consisted of a rectangular system without blast traps or subdivisions of any kind. This bomb would almost certainly have caused many additional blast casualties so that the total vulnerable area per ton may have been in excess of 2,000 sq.ft. per ton - about the same, against this type of bomb, as the small shelters we have described earlier in the chapter. Of course, tunnels at such a depth would be virtually safe against bombs of smaller calibre, such as would commonly be used in attacks on towns. Indeed, in considering the safety of the smaller shelters it is not necessary even to consider if the protection against specially heavy weapons is adequate. The necessity to do so in considering tunnel systems arises from the following considerations:-

(1) A tunnel system constructed to accommodate only a few people is an absurdity. If the overhead cover is to be adequate a large part of the cost will arise from the construction of entrances, shafts, etc., and these, once constructed, could probably without much addition be used to serve a tunnel system of much larger dimensions.

(2) A tunnel system will therefore be constructed only when a large number of people (say 5,000 - 30,000) are to be accommodated.

(3) The plan area of the system so constructed will be considerable; not less than about 1 acre per 2,000 persons, and thus with modern bombing technique it will be possible to be sure of hitting it with a limited number of aircraft, even if the bombs required are so large that each aircraft carries only one bomb.

(4) With a population scattered over the whole town in a large number of diminutive shelters it is useless, from the point of view of causing casualties, to attempt to aim at any selected point; but if a large number of persons are collected in a single shelter, it may very well be considered worth while, as part of a policy directed against public morale, to attack this shelter and to select that type of bomb which is necessary for the purpose.

Thus in designing small shelters, one has only to reckon with those weapons which are likely to be used for attacking any targets which happen to be in the district considered; but when a really large shelter is contemplated every weapon, including those which would be specifically selected to attack the shelter itself, must be taken into account. By collecting large numbers of people together in a tunnel one creates a target where none existed before.

A large tunnel system can therefore only be quite satisfactory if placed at a depth at which there is no possibility of perforation. What depth will in the future be necessary to meet this requirement is, of necessity, a matter for speculation. If we consider only weapons now produced*, it seems that about 160 ft. of chalk or equivalent depths in other rocks should suffice. But if a means is found to delay detonation in a weapon of a high-velocity rocket type, the equations of Chapter I show that this figure may become quite inadequate.

It should be noted that these considerations do not apply to the accommodation of small numbers of persons in existing tunnel systems provided that the cover is reasonably adequate. Where very large underground works exist at depths less than that required for complete safety it may even be possible to utilize them to accommodate a reasonable number of people provided that on the one hand the population density in plan is not large enough to present an attractive target to the enemy, and on the other hand that the tunnels are provided with such substantial sub-divisions that the effects of an internal explosion are confined within a reasonably small area.

8.6 The "calamity" risk

It will be realized that the remarks above in reference to tunnel systems applies, *mutatis mutandis*, to all large shelters. Not only is a large shelter more likely to be deliberately attacked, but, in addition, when successfully attacked, the large number of casualties resulting simultaneously constitutes a much more serious problem than an equal number distributed in a number of small incidents over a period of time. Rescue and medical services, for example, are very much better able to cope with a continuous trickle of casualties than with an equal number arriving together; and it is widely believed, though as far as the writer is aware, it cannot be proved, that such calamitous incidents have an adverse effect on morale.

For these reasons the British policy has been throughout this war to eliminate as far as possible the "calamity" risk by never concentrating a large number of people in a single shelter except when an extremely high degree of security could be offered. A large shelter, to be as safe as a small one, has to be a great deal safer.

* Written in June, 1945.

APPENDIX

THE DISTRIBUTION OF EXPENDITURE⁹

In the preceding pages, we have reviewed briefly the essential structural requirements in a shelter. We have shown that in many cases, advantage can be taken of existing buildings to provide protection better than that which could be provided ab initio for the same expenditure. Evidently then, the form which shelter provision should take in a given locality should be governed in many cases by the local conditions, by the nature of the existing buildings, by the local availability of materials, etc. Nevertheless, it is useful to consider briefly the quite general problem of the way in which a fixed expenditure, available for protection of a given area - say a large industrial town - should be distributed.

Suppose that the area under consideration can be divided into a number of localities of area $S_1 S_2 S_3 \dots$ sq. miles, in which the expected density of attack is $N_1 N_2 N_3 \dots$ ton/sq. mile, and suppose that the protection provided in these areas is such that the mean vulnerable area per ton for the inhabitants, (when allowance has been made for occupancy) is $A_1 A_2 A_3$. The chance that any one person will become a casualty is then $N_1 A_1, N_2 A_2, N_3 A_3$ respectively, provided that these fractions are small compared with unity and, if the population density is $D_1 D_2 D_3$, etc., the total number of casualties is -

$$N_1 A_1 D_1 S_1 + N_2 A_2 D_2 S_2 + N_3 A_3 D_3 S_3 \dots \dots \dots (8.6)$$

Now let us suppose that the relation between vulnerable area and cost per head of population is -

$$C = f(A)^{\#}$$

and that the values of C corresponding to A_1, A_2, A_3 , are C_1, C_2, C_3 .

Then we have the total expenditure C given by

$$D_1 S_1 C_1 + D_2 S_2 C_2 + D_3 S_3 C_3 + \dots = C \dots \dots \dots (8.7)$$

Various "policies" are of course possible. For example, we might decide that a constant expenditure per head of the population should be made throughout ($A_1 = A_2 = A_3, C_1 = C_2 = C_3$). In equity, it might be argued that everyone ought to run as nearly as possible an equal risk ($N_1 A_1 = N_2 A_2 = N_3 A_3$) or taking a somewhat more hard-headed view, that the objective is to minimize the total casualties given by (8.6) above.

If we accept the "equal risk" theory, we have of course -

$$A_1 = \frac{k}{N_1} \quad A_2 = \frac{k}{N_2} \quad \text{etc.} \quad \dots \dots \dots (8.8)$$

and k is determined by substituting C_1, C_2, C_3 in (8.6)

If we accept the "minimum total casualties" therefore, we can proceed as follows:-

Suppose that we make a small increase in the expenditure in zone (1) ΔC_1 , at the expense of zone (2). then we have

$$D_1 S_1 \Delta C_1 + D_2 S_2 \Delta C_2 = 0 \dots \dots \dots (8.9)$$

But
$$\Delta C_1 = \left(\frac{\partial f}{\partial A}\right)_1 (SA)_1 + \Delta C_2 = \left(\frac{\partial f}{\partial A}\right)_2 (SA)_2 \dots \dots \dots (8.10)$$

So thus
$$D_1 S_1 \left(\frac{\partial f}{\partial A}\right)_1 (SA)_1 + D_2 S_2 \left(\frac{\partial f}{\partial A}\right)_2 (SA)_2 = 0 \dots \dots \dots (8.11)$$

[#] It is here that the argument lacks generality. This function is not single valued but depends on the local circumstances.

Since the total number of casualties (8.6) is an absolute minimum, the effect of this small change in expenditure must be zero and

$$N_1 D_1 S_1 (\delta A)_1 + N_2 D_2 S_2 (\delta A)_2 = 0 \quad \dots\dots\dots (8.12)$$

Eliminating between (8.11) and (8.12) we find

$$\frac{1}{N_1} \left(\frac{\delta f}{\delta A} \right)_1 = \frac{1}{N_2} \left(\frac{\delta f}{\delta A} \right)_2 \quad \dots\dots\dots (8.13)$$

and by making similar small changes in C_3 , etc., we find that this equation can be extended to all indices and since on our hypothesis C is a function of A only, we can write -

$$N_1 \left(\frac{\delta R}{\delta C} \right)_1 = N_2 \left(\frac{\delta R}{\delta C} \right)_2 = N_3 \left(\frac{\delta R}{\delta C} \right)_3 \text{ etc. } \dots\dots\dots (8.14)$$

We note that if the equation relating cost and vulnerable area is of the form

$$A = A_0 C^{-K_C} \quad \dots\dots\dots (8.15)$$

the equation (8.7) obtained on the "equal risk" hypothesis is identical with equation (8.14) obtained on the "minimum casualties" hypothesis. In certain areas which do not lend themselves readily to any one type of protection, the equation may well be approximately true, but very often it will be found impossible to improve protection by increased expenditure, at the rate required by (8.15), so that if it is required to retain the "minimum casualties" hypothesis, there is nothing for it but to admit that the inhabitants of the most heavily attacked area must accept a greater risk[‡].

The defence of an essential command post, or military fortification, offers a parallel problem. Here the alternatives are to have one immensely strong erection, having an exceedingly small vulnerable area, or to have several duplicate posts of less strength. Suppose the vulnerable area of the single unit is A_1 , the density of attack being D_1 . Then the probability of destruction is $1 - e^{-A_1 D_1}$. In the alternative case, N similar units each have vulnerable area A_N and the probability that they will all be knocked out is:- $(1 - e^{-A_N D_1})^N$.

The cost of the single unit is C_1 , and for equal expenditure, the multiple units of course cost $C_N = \frac{C_1}{N}$. Thus duplication is undesirable provided that -

$$1 - e^{-A_1 D_1} < \left\{ 1 - e^{-A_N D_1} \right\}^N \frac{C_1}{C_2} \quad \dots\dots\dots (8.16)$$

Now if $A_1 D_1$ is small, equation (8.16) can be written in the form -

$$A_1 D_1 < (A_N D_1)^N \frac{C_1}{C_2}$$

or, for the case when duplication only is contemplated

$$A_1 D_1 < \sqrt{A_2 D_1}$$

Thus, for example when $A_1 D_1 = \frac{1}{100}$, duplication is worth while unless the single structure is ten times safer than each of the duplicates.

If $A_1 D_1$ is large (> 1) we proceed as follows:-

Duplication is undesirable if -

$$1 - e^{-A_1 D_1} < 1 - 2e^{-A_2 D_1} + e^{-2A_2 D_1}$$

$$e^{-A_1 D_1} > 2e^{-A_2 D_1} - e^{-2A_2 D_1}$$

[‡] This can be very easily demonstrated if we take occupancy into account. Suppose that a Morrison shelter has a vulnerable area $\frac{1}{3}$ that of an unprotected house, and that its "occupancy" is 80 per cent. Then in an area attacked three times as heavily, a perfect shelter (one of vulnerable area zero) would have to have an occupancy of 95 per cent - an almost impossibly high figure - to give an equal risk).

Now since A_2D_1 is still larger, the last term can be neglected, and we have duplication undesirable if

$$\begin{array}{ll} e^{A_1D_1} & \frac{1}{2} e^{A_2D_1} \\ A_1D_1 & A_2D_1 + \log \frac{1}{2} \end{array}$$

Thus the larger A_1D_1 becomes the smaller must be the ratio A_2/A_1 in order that duplication may be worth while. If the risk to the single installation is high ($A_1D_1 \gg 1$) the duplicates have to be almost as safe as the original in order to offer any advantage. Duplication of defences is an excellent means of eliminating the risk of an unlikely calamity, but it is almost useless for buttressing a forlorn hope.

Of course, in the example we have quoted there are many other factors to be taken into account; for example, the persons manning the fortification may have their own opinion as to how strong it should be; but there are many installations, such as communication cables, power supply systems, etc. in which the whole basis of the problem is summed up in the few lines above.

REFERENCES

- 1 R. & E. Department "The wounding power of debris" R.C.423, July, 1944.
- 2 Black, A.N., Christopherson, D.G., and Zuckerman, S. "Fractures of the head and feet" R. & E. Department R.C.334, July, 1942.
- 3 Burns, B. Delisle, and Zuckerman, S. "The wounding power of small bomb and shell fragments" R. & E. Department R.C.350, October, 1942.
- 4 Fisher, R.B., Kröhn, P.L. and Zuckerman, S. "The relationship between body size and the lethal effects of blast" R. & E. Department R.C.284, October, 1941.
- 5 See also R. & E. Department "A study of the safety/cost relation in different types of dwelling" R.E.N.177, October, 1942.
- 6 This and the following tables are taken from R. & E. Department "The relative effectiveness of various types of shelters against flying bomb attacks" R.E.N.464, January, 1945.
- 7 Zuckerman, S. "The field survey of air raid casualties" R. & E. Department R.C.270, November, 1941.
- 8 See for example:- Walley, F. "Movement of shelters due to earthshock" R. & E. Department R.C.287, January, 1942. In this paper it is shown that the maximum velocity imparted to the standard surface shelter as a whole, from a 250 kg. bomb at 15 ft. horizontally from the shelter wall, and 12 ft. 6 in. deep is about 10 ft.-sec. somewhat less than that imparted to the ground at the point in the absence of any surface load.
- 9 The argument here given will be found in more detail in R. & E. Department "Protective measures in new dwellings: an approach to the policy of expenditure" R.C.330A, June, 1942.

BIBLIOGRAPHY OF THE SHELTER PROBLEM

R. & E. Department, Ministry of Home Security:-

- R.C.33 Explosion trials on four trench linings. September, 1939.
- R.C.50) Bombing tests on trench linings, Larkhill (chalk subsoil), October, 1939.
R.C.51)
- R.C.55 Tests on six trench linings at Larkhill, forming the second series. November, 1939.
- R.C.68 Bombing tests on trench linings, Stewartby (clay subsoil). January, 1940.
- R.C.96 Bombing tests on concrete shelter linings, brick shelters, and steel frame at Stewartby (clay subsoil). May 1940.
- R.C.217 Tests on brick surface shelters at Stewartby. April, 1941.
- R.C.225 Report on tests on (a) reinforced concrete shelters (b) methods of strengthening brick surface shelters, Richmond Park. Groups 1 and 2. July, 1941.
- R.C.272 Report on tests: methods of strengthening brick surface shelters. November, 1941.
- R.C.285 Report on tests on reinforced concrete shelters, Richmond Park. Group 5. December, 1941.

- R.C.355 Report on tests on four 'factory type' brick surface shelters, Richmond Park. Group VI. October, 1942.
- R.C.356 Report on tests on three surface shelters, Richmond Park. Group VII. October, 1942.
- R.C.215 Report of test on semi-sunk domestic shelters, Stewartby. June, 1941.
- R.C.242 Test on tunnel shelter at Epsom Downs. July, 1941.
- R.C.298 Note on Mansfield tunnel experiments. January, 1942.
- R.C.262 Note on the siting and construction of air-raid shelter tunnels.
- R.C.295 Note on a new standard for reinforced shelters. January, 1942.








FIG. 8-1 ANDERSON SHELTER




ALL SHEETS TO BE 1/8 GAUGE
ALL BOLTS 3/8 WHIT




Group 5



Shelter No 2-Reinforced Concrete Shelter Test at Richmond Park. FIG. 8.3.




Plan Scale of Feet 0 2 4 6 8 10 12 14 16 18 20 1/4" = 12' CS.



PLAN




SECTION A-A



SHELTER TESTS AT RICHMOND PARK
GROUP 8. SHELTER 3

Fig. 8.4

- Shelter N^o 1 - Reinforced concrete.
- Shelter N^o 2 - Reinforced brick skin.
- Shelter N^o 3 - Normal type.
- Shelter N^o 4 - R.C. inner skin with base plates.
- Shelter N^o 5 - do: with R.C footings under wall.
- Shelter N^o 6 - R.C. inner skin with floor.



GROUP 1.
PROPOSED SHELTER TEST
TO BE HELD AT RICHMOND PARK

FIG. 8.5.








Fig.8.6 Effect of ground-shock from a buried bomb on a group of unreinforced brick surface shelters. The roof of the shelter on the left is seen separated from the walls while that next to it has its back broken by the movement. (Paragraph 8 & 31)




Fig.8.7 Effect of ground-shock on a group of reinforced brick surface shelters and one reinforced concrete shelter (on extreme left). Note how shelters are thrown into the air without fracture. (Paragraph 8)



Plan
Group 4. Reinforcement of Shelter No 1

FIG. 8-8



Group 4. Communal Shelters - Details of Reinforcement.





FIG. 8-10.

FINAL DESIGN OF INDOOR TABLE SHELTER.




Photo 1.




Photo 3.

Fig. 8.11

Falling floor impact test on indoor shelter.

CHAPTER IX

"BOMB-PROOF" SHELTERS AND FORTIFICATIONS

9.1 The meaning of "bomb-proof" and "bomb-resisting"

Ten years ago the word "bomb-proof" was self-explanatory. A building was "bomb-proof" if it could not be seriously damaged by any bomb capable of being carried in an existing aircraft. Even then, the requirements for a "bomb-proof" shelter were onerous, and necessitated extremely heavy construction, but they were within the bounds of possibility, provided that only a moderate amount of "bomb-proof" accommodation was required within the building.

At the beginning of the war, it was realized however, that a shelter, designed to be proof against the largest bombs then in service or under development, would require an expenditure of labour and material so large that it could only be justified in very exceptional circumstances. A few such "1939 bomb-proof" shelters or "fortresses" were constructed, mostly for housing an operational command headquarters of the fighting services, and this standard of construction became known as "fortress protection". Judged by 1945 standards, it is not completely bomb-proof, and indeed it is very doubtful if there exist anywhere, constructions capable of resisting the largest penetrating bombs now in use.[‡]

Between the small shelters described in the last chapter, and the "fortresses" there was a very wide gap, both in safety and expenditure, and to bridge it a third standard of protection was introduced - the so-called "bomb-resisting" shelter designed to be safe against bombs up to weight 500 lb. This standard necessitated a roof about 6 ft. thick in reinforced concrete (as opposed to the 10-12 ft. roof of the fortress) the other dimensions - walls, and floors, - being in proportion. Although not many shelters of the bomb-resisting type were built in Great Britain, we have considerable direct evidence of its behaviour, a very similar standard having been widely used by our opponents. Many fortifications of the "Atlantic wall" were constructed approximately to this standard; and also a number of the formidable "Bunker" shelters, erected in the cities of western Germany, when it became clear that an effective reply was being made to the earlier German attacks on British industry. Naturally, a good deal of experimental work was done in this country, in order to develop means of attacking the Atlantic wall and the Bunker shelters were often hit during our large-scale industrial raids.

Finally, a reference must be made to the last attempt made by the Germans to attain truly "bomb-proof" construction - in the submarine pens on the Atlantic coast, and on the "large sites", the huge concrete erections in the Pas de Calais which were intended to provide safe bases from which various "V" weapons could be aimed at London. When planned, these structures were undoubtedly believed to be practically bomb-proof (their roof thickness was over 16 ft.). The air campaign by which they were defeated forms not the least interesting narrative of the war.

For the present purpose, we need make no distinction between shelters and fortifications. The latter are simply shelters with a special purpose which may modify their form, for example, by necessitating an embrasure, which somewhat decreases the protection afforded, but in general the principles of design will be the same regardless of the purpose for which the shelter is intended.

Furthermore, whereas in dealing with small shelters, we had at our disposal a number of totally different types of protection involving different materials used in different ways, in the present chapter we shall deal almost exclusively with one material - reinforced concrete - and the general form of the protection offered will not vary much. We shall find as before that both surface and sub-surface shelters are possible in various conditions and that a wide range of geometrical shapes can be considered. In all types, however, we must provide a roof capable of resisting perforation, walls capable of resisting near-misses, whether in air or in earth, and a floor to resist the earth-shock from a more or less remote burst. Very occasionally, we may consider the use of armour plate for a special purpose, but the introduction of an entirely new type of "bomb-resisting" shelter on an entirely new principle (as the Morrison was introduced in the middle of the war) seems most unlikely.

[‡] We exclude a number of very deep tunnels, mines, etc., which are not constructions in this sense.

9.2 Methods of attack - direct hit and near-miss

Obviously any structure is liable to receive a direct hit or a near-miss. The larger the plan area of this target the more important relatively will be the former. In the very small shelters described in the preceding chapter we were able to give a very fair measure of protection without attempting to provide any defence whatever against a direct hit from any but the very smallest bombs. Our whole aim was to reduce the area in which a near-miss could inflict serious damage. At the other extreme, in the expanses of the submarine pens, often many acres in extent, the risk of serious damage by a near-miss was practically trivial, and the whole purpose of the designer was first to provide a roof which would prevent perforations, and secondly, if this was impossible, to subdivide the interior in such a way that the area of damage caused by a bomb exploding inside was as far as possible restricted.

The bombs required for an attack on a heavy concrete structure differ according to whether the primary aim is to effect damage by direct hit or by near-miss. The near-miss attack requires an "M.C." bomb of charge-weight ratio about 50 per cent, which will probably, though not certainly, break up or detonate prematurely in the event of a direct hit. Two or three special types of bombs can be used for a "direct hit" attack; in general the charge-weight ratio of each is below 50 per cent and so, if a near-miss is scored the earth-shock or blast damage will be less than would be the case with the M.C. type. Accordingly the attacker must make up his mind beforehand whether his primary aim is to score direct hits or near-misses, and must select his bombs appropriately, knowing that if by chance his bombs score in the other category he will achieve less than maximum damage.

In practice, his choice is often influenced by the fact that his target consists not only of a number of heavy concrete structures but also of a complex system associated with them. In fortifications, for example, there are likely to be trench systems for local defence, cables for power and communications, roads or railways for supply purposes and so on. All these targets are best attacked by M.C. bombs, and for this reason the attacker will endeavour to retain these bombs - the near-miss type - wherever possible. A useful though inexact rule is that where the minimum weight of the bomb necessary to perforate the roof exceeds that of the bomb whose crater diameter (delay-fuzed) equals the width of the structure (the minimum plan dimension) then the attack should be by near-miss.

It follows that there is a certain limit beyond which it is useless to strengthen a small surface or sub-surface shelter.* Suppose its diameter is 30 ft. and that its floor is not more than 20 ft. below the surface, then a near-miss by an M.C. bomb of weight 4,000 lb. making a crater 60 ft. across will blow it out of the ground and will almost certainly put its occupants out of action. A shelter of this size cannot therefore be protected against 4,000 lb. bombs, and thus to provide it with a roof more than about 12 ft. thick, with a view to resisting bombs of this size or larger is practically useless. It will only prove useful if by some mischance the enemy elects to attack by direct hit. Of course, a shelter of the dimensions given is a most uneconomical proposition. A roof of this thickness can seldom be justified unless it provides a considerable protected space.

We have now to consider in detail the five main causes of damage to heavy concrete installations:-

- (i) Direct hit, with instantaneous fuze: explosion in contact with roof.
- (ii) Direct hit, with delay fuze: penetration or perforation followed by explosion.
- (iii) Near miss, with instantaneous fuze: explosion near or in contact with walls above ground level.
- (iv) Near miss, with delay fuze: explosion near or in contact with walls below ground level.
- (v) Near miss, with delay fuze: explosion below shelter near or in contact with floor.

* Assumed to be built on penetrable soil. On hard rock very great strength is possible in a small shelter.

We have already in Chapter I dealt at some length with the question of penetration, and in Chapter IV we have given some consideration to the effect of near explosions in earth. Some account must now be given of the effect of contact and very near explosions in air, and we must give further attention to contact explosions below the surface under conditions of confinement.

9.3 Contact explosions in air

Earlier in this book it has usually been possible to describe the effects observed simply in terms of the weight of the charge, and its position relative to the target. We can add definition to this latter phrase by referring always to the position of the centre of mass of the explosive. When we come to the study of contact explosions, however, it is no longer possible to leave out of account the effect of the shape of the charge, and as every student of demolition technique knows, the "closeness of contact", or absence of the most tenuous layer of air between charge and target has an important effect in increasing damage[‡].

For our present purpose, however, we are assuming that the attack is by projectiles, whether air-borne or not, which are of a quite unsuitable shape for establishing geometrically close contact with the plane surfaces of a fortification. We can, therefore, assume that the attacker does not in general enjoy the benefits of a real contact shot,^{‡‡} and in what follows we assume that contact is never closer than might be obtained by placing the charge against the surface without any special precautions.

In practice we are interested chiefly in a cylindrical charge of length about three to four times its diameter, either lying on the target with its axis parallel to the surface (the "sideways-on") or standing normal to it, with one end in contact (the "nose-on" position). For the most part we shall be interested in cased-charges, of medium or low charge-weight ratio, though we have little or no evidence that case weight is a matter of importance, when contact charges are under consideration.

The experimental evidence on this subject is not as complete as one could wish. A few generalizations, derived for the most part from small-scale experiments, may first be quoted.

- (i) Light reinforcement does not have much influence in the size of the surface crater formed by a contact charge, but reinforcement near the rear face, particularly if in the form of a close mesh, may have an important effect in reducing scabbing.¹
- (ii) The crater volume varies approximately inversely as the square root of the concrete crushing strength. The tendency is for the depth of the crater to vary more than the diameter as the crushing strength varies². There does not seem to be any very substantial correlation between the total thickness scabbed and the crushing strength³ provided that the latter falls within reasonable limits (say 2,000-7,000 lb./sq.in.)
- (iii) The crater made in a slab only just thick enough to resist the explosion is substantially smaller than that in a thicker slab.³ This somewhat curious result might perhaps be used as a starting point in the further investigation of the mechanism of crater formation.

In Table 9.1 we give the results of a few full-scale and small-scale tests. These results are not complete; they do not, for example, enable us to say what is the minimum scabbing plate or rear mesh of reinforcing which will produce the effects described. However, they do suggest the following conclusion:- A mesh of mild steel reinforcement of the order of 0.5-1 per cent by volume, concentrated near the inner face will retain the shattered concrete in the scab from a sideways-on

‡ Except in the one important case - that of the "shaped" Monroe charge - which, as we describe below, works best with a specified "offset" or space between charge and target.

‡‡ Some small bombs have been constructed with plastic explosives which are supposed to flatten themselves into close contact on striking the target. Some infantry anti-tank weapons are of this type, but it has not been used on any appreciable scale for aircraft bombs or shells.

contact explosion and will not bulge outwards by more than about $1/7$ span (an acceptable maximum) provided that the thickness of concrete (inches) exceeds nine times the cube root of the charge-weight (lb.) (TNT or amatol). Similar tests have shown that under the same conditions for an explosion in the "nose-on" position, the necessary thickness of concrete (in.) will be about five times the cube root of the charge weight (lb.) of T.N.T. and that in the absence of a rear scabbing or "soffit" plate, the concrete cover on the inside reinforcing will be displaced more or less violently unless the thickness is about double that specified. The use of the steel soffit plate on the interior surface is desirable in almost all cases. Very often this plate can be made to take the place of shuttering during construction, and thus serve a double purpose.

Other experiments have thrown light on the effect of detonating a charge "nose-on" in a crater of the dimensions formed by the impact of a bomb of the corresponding size. Provided that the target slab is thick enough to resist the impact penetration and scabbing at (say) 900 ft./sec. the subsequent explosion is not likely to add greatly to the damage, particularly if a soffit plate is provided. The crater diameter is enlarged by the detonation, but its depth is often practically unchanged. It is a curious point that the thickness of concrete required to resist impact scabbing by M.C. bombs dropped from high levels, is very nearly the same as that required to resist the side-on contact explosion of the same bomb, which might occur in a low-level attack with an anti-ricochet device. The following table of proof thickness calculated from the equations of Chapter I and from the rules given above will make this clear:-

TABLE 9.2

PROOF THICKNESS FOR BOMB-PROOF ROOFS

Bomb (German medium-case type)	Penetration at 1000 ft./sec. (in) (i)	Thickness perforated at 1000 ft./sec. (in) (ii)	"Proof" thickness to resist scabbing (iii)	Proof thickness to resist perfor- ation by side- ways-on contact shot (in)‡ (iv)
50 kg. S.C.	15	26	35	34
250 " "	27	47	64	59
500 " "	36	61	82	71
1000 " "	41	75	111	93

We note that the difference between column (i) and column (iii) always exceeds $5/9$ x column (iv), the thickness perforated by a nose-on shot.

The use of a high charge-weight ratio bomb would increase the thickness necessary to resist the sideways-on explosion without increasing the load on the aircraft, but in general this form of attack is not greatly to be feared. At best it can do only local damage in the interior, less serious than that which will be caused by an internal explosion after perforation of even a small bomb.

The experimental evidence on the question of the effect of decreasing the percentage of reinforcing is quite inadequate. The argument of Chapter VII suggests that a reduction from m per cent to n per cent in the percentage of steel, (retaining the same distribution) will reduce the energy-mass product in ratio not exceeding n/m . If, as is probably the case for the very large thickness-span ratios which we are dealing with here, a large proportion of the strength comes not from tension in the reinforcing but from arch action in the concrete, then reduction in the percentage reinforcing will have an even smaller influence on the resistance. An increase in thickness from t to t', however,

‡ The presence of rear reinforcing and scabbing plate is assumed.

produces an increase in the energy-mass products of at least $(\frac{t'}{t})^2$ or $(\frac{t'}{t})^3$

if arch action is important. Thus, as far as resistance to "bulging" and "general" deformation is concerned, a reduction from m per cent steel to n per cent steel is likely to be offset by an increase in thickness from t to t' given by:-

$$\frac{t'}{t} = p \frac{m}{n}$$

when the parameter p is unlikely to be less than about 3.

The factor of real importance however, is not so much bulging as local damage, cratering and scabbing. Reinforcement has little if any effect in reducing cratering, but it has an important influence in retaining the scab. What is essential for this purpose is not that the reinforcing bars should be heavy, - the bars in the rear face of a slab are seldom cut, even when the slab is completely holed by an explosion,* - but that they should form a very close mesh, well anchored by through bars into the interior and thus capable of retaining the concrete even when considerable shattering has taken place. What is wanted therefore is not a high percentage of all-through reinforcement (a close mesh through the whole of the very thick walls and roofs which we are here considering will only increase the difficulty of pouring a high strength concrete) but a very close mesh of small bars near the inner surface, well tied to a comparatively wide mesh in the solid, which simply serves to prevent the general shattering to be expected in unreinforced concrete. The system of reinforcing shown in Fig. 9.6b, although it totals no more than 0.34 per cent by volume on the average would probably be capable of standing up quite as well as those whose tests are referred to in Table 9.1. Of course, it is assumed throughout that the reinforcing is such that the roof has an adequate factor of safety under ordinary static gravity forces. In most cases, this requirement will be met by the type of reinforcing which we have specified for providing resistance to explosion, particularly as the supported span of the roof is usually only a few times its thickness. Where a large open space is required beneath a heavy roof, it will sometimes be found that extra tension reinforcing must be added in order to provide an adequate factor of safety against ordinary bending forces.

It is not easy to specify exactly what constitutes this "adequate factor of safety". If the roof is so large that surface craters made by small or medium calibre bombs are not likely to cover an appreciable part of the total area, a normal working stress of perhaps 7 ton/sq.in. in the steel is, perhaps, permissible (note that since we are dealing here with static forces, it would be quite wrong to base calculations on the yield stress as in Chapter VII). If, however, for some reason, the roof is narrow and supported at its ends only, so that it forms a beam whose average depth might be decreased appreciably by a surface crater, a much lower working stress - say 4 ton/sq.in. - is desirable.

9.4 The attack by shaped charges

We have now to consider an entirely different form of explosive charge, which, although it explodes in air in close proximity to the target, is in no sense comparable with the ordinary shattering contact charge. It has been known for many years that a charge of cylindrical form having one end hollowed out into a conical cavity will produce results of unprecedented severity in the direction of the hollow end. Such charges, which are sometimes referred to as "Monroe" charges, have been developed for many purposes during the war. It has been found that their directional effect is much enhanced by lining the conical cavity with a metallic layer. When the charge explodes, this liner is ejected along the Axis of the cylinder at a very high speed, as a jet of liquid or gaseous metal. This jet is in effect a very high velocity projectile, and instead of shattering the concrete it bores a narrow hole, similar to that formed by an armour-piercing shot but much deeper. An 80 lb. shaped charge for example, is capable of forming a hole of 2 in. diameter clean through 10 ft. of reinforced concrete, and of producing a not inconsiderable blast effect locally on the far side.

* It is a curious feature that under these conditions the exposed bars may show several incipient "necks" like those produced just before fracture in a static tensile test.

These charges have not been used to any large extent in aerial bombing up to the present time but clearly they could be so used in at least two ways. Either a large number of charges could be dropped each of which would cause a small area of damage in the interior of the fortification, or a single larger charge might form a hole through which a smaller fragmentation or demolition bomb, originally placed behind the charge, might enter.

The very great penetrative powers of the shaped charge makes the "natural" method of defence - by increasing roof thicknesses - practically an impossibility; instead methods of defence based on the properties of the weapon itself must be contemplated. To produce its optimum effect, the charge must be offset, i.e. it must be fired a short distance (about one charge diameter) away from the surface attacked. If this surface is a perfectly plane one there is of course no difficulty in arranging this:- a false nose containing a rapid fuze can be provided in front of the explosive. If the roof is provided with a comparatively light "burster" placed some distance above the true roof, the explosion will take place in a position remote from that required for optimum performance. If the burster is inclined - for example, if it takes the form of an ordinary pitched roof - the situation may be still better, as not only is the fuze problem more difficult, but also the charge may be deflected from the normal before explosion, and thus forced to bore through a greater thickness of concrete before reaching the interior. Furthermore in these circumstances it is not unlikely that the "follow through" portion of the weapon, if it has one, will fail to find its way through the hole provided for it by the leading portion.

It is the common practice of the enemy to erect substantial pitched roofs over fortifications and large concrete shelters for camouflage or perhaps for aesthetic purposes. These roofs have not proved very effective, at least as far as camouflage is concerned, but it may well be that the further development of the shaped charge would make such measures a necessity.

9.3 Contact explosions in earth

Obviously, the confinement afforded by the earth, when a bomb explodes in contact with a concrete structure but below ground level, will greatly increase the forces to which the structure is subjected. Accordingly underground walls must be made heavier, if the same standard of resistance is required. Moreover, the shape effect is less important in earth, and the difference between "side-on" and "end-on" shots is much less marked.

In Table 9.3 we summarize the results of three full-scale experiments carried out to determine the critical thickness of concrete required to resist a side-on contact explosion in earth. These experiments were designed primarily to verify the dimensional theory under these conditions, and, although the method of support of the panels tested was not exactly scaled, it was found that over the small range of linear scales investigated there was no appreciable deviation from the theory. Comparison with small-scale tests, however, indicates that, as usual, the model work underestimates the damage slightly.

TABLE 9.3
CONTACT EXPLOSIONS ON CONCRETE - FULL-SCALE TESTS IN EARTH

Bomb	Charge-weight of Bomb (lb.)	Thickness of slab t (in.)	Reinforcement	Scabbing plate [‡]	$t/W^{1/3}$	Damage
50 kg. S.C. ⁶ (side-on)	52	49	0.75 Two thirds near inner face One third near centre	No.	13	Wall partly shattered and bulged outwards by 0.5 span. Concrete cover on interior face scabbed off.
250 lb. AS ⁶ (side-on)	132	66	ditto	No.	13	Wall partly shattered and bowed 0.3 span. Concrete interior cover scabbed off, and projected across interior.
250 kg. S.C. ⁶ side-on	275	84	ditto	No.	13	Wall partly shattered and bowed 0.43 span ^{‡‡} . Concrete interior cover scabbed off & projected across interior.

[‡] In subsequent small-scale experiments, it was shown that scabbing plate placed within the interior layer of reinforcing (which was left bare,) prevented the discharge of concrete from the interior surface, but did not reduce the bulging of the panel as a whole.

^{‡‡} See overleaf.

The experiments listed in Table 9.3 indicate that a concrete wall, reinforced 0.75 per cent by volume of steel, with two-thirds of the reinforcing at the inner face, and subjected to the sideways-on contact explosion in earth of a bomb of charge-weight W lb. (TNT or amatol) will bulge a maximum distance equal to about half of the span if its thickness is given by $t/W\sqrt{3} = 13$. To reduce this deflection to our standard value $1/7$ th span, would require $t = 17W\sqrt{3}$. Experiments in the United States⁷ have given a very similar result.

In the absence of a scabbing plate the concrete cover over the inside layer of reinforcement is detached and projected with some violence into the interior. The use of a steel lining is therefore as desirable here as when the explosion takes place in air.

9.6 The minimum thickness of floors

In the above paragraph we have been concerned mainly with the specification of the minimum thickness of an underground wall. The situation with regard to floors is somewhat different particularly if the fortification is small. (In a large building, capable of resisting penetration, an explosion under the floor cannot occur, except near the exterior walls from a bomb entering the ground obliquely, and so appropriate reductions of floor thickness in the interior can be made). An investigation of the position in which the explosion can take place in order to inflict a specified degree of damage on a floor of thickness $5W\sqrt{3}$ with the standard reinforcing has been made and its results are shown in Fig. 9.1. It should be noted that the ratio deflection/span used to define "heavy damage" is less than we have considered acceptable for walls. For a small "pill-box" of type investigated (about $48W\sqrt{3}$ in diameter; say 24 ft. across when the attack is by 500 lb. bomb) the decisive factor is not the damage to the floor itself but the fact that the whole structure is thrown into the air with velocity large enough to cause injuries in the interior whenever the explosion is within the volume indicated as causing "light damage". If the structure forms part of a larger unit, its velocity will of course be reduced but at the same time the local damage will become more severe, as the block movement of the whole is prevented. In Chapter XI we discuss in some detail the parallel problem of the effect of the movement of supports on the damage to a panel wall. All that need be said here is that whether the unit stands by itself, or forms part of a large structure, the reduction of the floor thickness to $5W\sqrt{3}$ can only be considered acceptable if the bomb is prevented from exploding in the area marked "light damage" in Fig. 9.1.

9.7 Geometrical considerations in design

In the preceding paragraphs we have laid down the fundamental dimensions of the fortification; we have showed that those portions of the exterior surface which are below ground level but are not inaccessible to contact explosions must be made far stronger than the above-ground portions, and we have stated that if the aim is to secure complete protection against a given size of missile, then the roof, and the above-ground portions of the walls must be approximately of the same thickness.

Our problem now is to examine the geometrical forms which can most achieve these standards most economically. Two generalizations can be made a priori

- (i) A fortification of approximately cubical form will involve less expenditure of concrete per unit volume protected than (say) a flat structure of larger area.
- (ii) Surface fortifications will be in general more economical than those partly or entirely sunk in the ground.

Several possible forms each intended for protection against the 500 lb. bomb are shown in Fig. 9.29. In these forms, the above-ground wall thickness is somewhat below our recommendation, and the roof thickness somewhat above, because of the severity of damage resulting from a perforation when compared with even the closest near-miss. The floor thickness has been reduced to 36 in. (about $5W\sqrt{3}$) provided that the bomb cannot reach the "medium damage" zone as shown in Fig. 9.1 unless its path length in the soil exceeds 20 ft. In practice, it can be shown

~~see~~ (see previous page)

In this test the edge support was inadequate and gave way somewhat; the total deflection at the centre of the wall was therefore greater than the bulge.

that even if the path length of the bomb in this material is 30 ft. the probability that its track will bring it into the danger zone is extremely small. In case 2, where a burster slab is used to prevent the bomb reaching the zone in which floor damage is to be expected, the thickness of this slab is taken as only $1\frac{1}{3}$ times the penetration of the bomb. Since the slab is earth-backed and not suspended, the effect of scabbing in increasing perforation will be less marked. For the same reason, little or no reinforcing is necessary in a burster. A further possibility is to place the burster vertically below the exterior wall, as a "skirt" or "curtain" wall.¹⁰ So placed, it is equally effective in preventing the bomb from reaching the floor-damage zone, and although it may be damaged by earth-shock from near-misses this damage is without importance since it does not affect the fortification itself.

9.8 Structural considerations in design

It will be quite clear that constructions of the type shown in the figure gain much of their strength from their continuity. Weaknesses at the junction of roof and walls, or of walls and floor, must be eliminated. It is essential that the concrete throughout the fortification should be as nearly as possible continuous and homogenous. In practice however construction joints between batches and pours are inevitable. A few principles can be laid down as to the way in which such joints should be sited.

(i) Joints should if possible run parallel to and not across the exterior surfaces, i.e., they should run horizontally in roofs, and floors; in walls vertically and parallel with the direction of the wall. All units should, however, be poured with the fewest possible number of joints. Not more than two or three lifts should be necessary in even the thickest roofs.

(ii) In roofs of very large area vertical joints may be essential both from considerations of thermal expansion and because the quantity of concrete required to pour a single lift over the whole area is beyond the capacity of the available plant. In these cases the vertical joints should be differently placed in the various lifts, so that no vertical joint runs through more than say one-third of the total thickness, and, if possible, all joints should be situated over division walls.

(iii) It may well be desirable to provide additional shear reinforcing at joints in the concrete, so that the shear strength at these points is as great as elsewhere.

It is also essential that reinforcement should be made as continuous as possible. This can best be done by welding successive lengths of bars together, or by hooking with an adequate overlap. Where the end of a bar is held by bond with concrete only, a lap length of not less than 72 diameters is recommended.

In prescribing continuity we must, however, make a clear distinction between those parts of the structure which are essential and those which are not. In Fig. 9.2 cases 1, 3 and 4, the structure forms a single unit, and everything must be done to ensure its continuity. In case 2 the structure itself is surrounded by a burster slab whose sole purpose is to prevent the bomb reaching a place in which it might damage the essential unit. It would be wrong under these conditions to make the burster continuous with the structure; it is quite true that to do so would decrease the damage to the burster slab, but only at the expense of increasing damage to the fortification itself. Damage to the burster is quite without importance and so the risk, however, small, that a continuous joint between burster and floor will increase the damage to the latter, should not be run.

A similar principle has been suggested for the design of fortifications in which one part has much greater importance than the remainder. As an

example of such a case we may quote the large gun emplacement, shown diagrammatically in Fig. 9.3. Here the vital item is the gun itself, but various magazines, stores, etc., are also necessary. The gun, on its large foundation slab is placed in the centre, and round it are constructed the "supply" shelters. A direct hit on the gun, capable of penetrating its overhead protection puts it out of action, but a direct hit on a magazine does not necessarily do so, since there are other magazines which may be drawn on. The surrounding structures must prevent penetration below or nearly below the foundation slab of the gun, as even a small movement of this slab will have fatal effects on the accuracy of fire. Finally, the displacement of the subsidiaries, resulting from a near miss must be prevented from causing any movement of the central slab. Clearly this is best done by permitting a completely free joint, or even a small air-gap between the central slab and the surrounding ring. Each unit - the gun, and the "supply" ring - must be as rigid, and as closely integrated as possible, but movement of the one relative to the other should not be retarded in any way.

9.9 Special technique during construction

We have already referred to the necessity for careful control of the pouring procedure during construction, the necessity for careful siting of joints, etc. Some other points arising from the very great thickness and weight of units are worthy of consideration.

(a) Placing of reinforcement. In fabricating a very thick slab, a mesh of reinforcement which may be 16 or 20 ft. thick must be laid beforehand, and must form a rigid framework, which will not distort awkwardly during pouring. The heavy reinforcement running through the thickness of the slab, which we have recommended as a precaution against scabbing, will be useful in imparting the necessary rigidity to this framework during erection. A system of reinforcing which has been very widely used, however, is the so-called "cubic mesh", which consists simply in three mutually perpendicular sets of bars of the same diameter, with the same spacing (usually 1 ft.) in each direction. This system is clearly not the most economical in steel, since it affords neither a concentration of bars on the inner face, nor a reduction near the outer face. On the other hand, it is of course, extremely simple in erection and this consideration has frequently outweighed that of economy when fortifications have had to be erected by unskilled or semi-skilled labour.

(b) Pouring of concrete. Given that reinforcement is placed at about one foot average spacing it is usually considered that aggregate size must be limited to a maximum of 2 inches[‡]. Larger aggregates will give better resistance to penetration (for a given water-cement ratio) but difficulties of consolidation will generally preclude their use. Even with this limitation the problem of achieving a high density concrete when pouring through a 16 ft. thick mesh of steel bars is considerable, and necessitates the use of a much wetter mix than would be desirable on other grounds. Of course, when the concrete surface is accessible, ordinary methods of consolidation by vibration can be used, and thus near the upper face of a roof the large aggregate size and low water-cement ratio so desirable in resisting penetration can be introduced particularly if, as we recommend, the percentage reinforcement has been substantially reduced in this region. In principle, on the inside face of a slab, the reinforcing is the dominant factor, and the design of concrete must be adapted to suit the steel. On the outside face the converse is the case. We have here an additional argument for pouring a roof in horizontal layers rather than in vertical sections.

‡ Of course, the presence of a very close reinforcing mesh on the inner face of a slab like that shown in Fig. 9.6 can be disregarded in selecting the maximum aggregate size. It is our deliberate intention that the aggregate should not pass through this mesh.

(c) The provision of the soffit or spalling plate. We have repeatedly argued in this chapter that all interior surfaces, with the possible exception of floors, should be given a steel lining. The practical engineering of this requirement can be approached in several ways. Two of the three here described are particularly adapted to roofs while the third is applicable mostly to walls.

(i) The "filler joist" method in roofs. This method consists simply in placing steel joists across the shorter span of the roof usually at about 1 - 3 ft. spacing, and filling the gaps between them with steel plate preferably welded to the lower flange, as shown in Fig. 9.4a. It is essential that the joists should be long enough to ensure that they will not pull off the supporting walls even when very badly bowed downwards. Their end anchorage can be improved by passing the vertical reinforcing bars in the supporting walls through holes drilled in the flanges, so as to ensure that the joist extends when bowed downward, and does not merely pull out of the concrete. If this is done it is permissible to include the steel in the joist in the computation of the percentage reinforcing in the lower layer of the roof, and thus to reduce somewhat the weight of steel in the body of the concrete, though this should not be allowed to fall below about 0.1 per cent, the minimum necessary to prevent widespread shattering. The steel in the scabbing plate itself, however, should not be included in this computation, since the roof can be deflected without appreciably extending it. The plate should not be less than $3/16$ in. thick. Where possible joists should be made continuous over partition walls, and between successive portions of the building, though not, of course, where the free joints referred to above are required.

(ii) The "steel troughing" method in roofs. This method, illustrated diagrammatically in Fig. 9.4b, consists simply in covering the area of the roof with steel troughs placed across the shorter span and welded together. It is again essential that the troughs should be prevented from pulling off their end support, and accordingly wall reinforcement should be passed through holes drilled for the purpose. It is sometimes recommended that the bottom layer of steel in the roof concrete should also be either passed through the troughs or welded to them, in order to ensure bond between steel and concrete over the whole length. Since the steel only plays its real part when the concrete is already shattered as a result of spalling this measure may not be necessary.

Here again an allowance can be made for the weight of steel in the troughing in computing the percentage of reinforcement in the roof.

Both these methods have the advantage that they provide shuttering on the underside of the roof capable of sustaining a considerable load of concrete during pouring, and thus greatly simplifying the support of the roof during construction.

(iii) The plate-between-bars method in walls. It is clear that if methods (i) and (ii) are adopted both in roof and in walls difficulties may arise in securing an adequate anchorage at the joint for both sets of members: furthermore the strong shuttering afforded by these methods is not required on a vertical surface. For these reasons, the alternative shown in Fig. 9.4c has been evolved, and has proved satisfactory in an experiment. Here the steel spalling plate, which again must not be thinner than $3/16$ in., is inserted between the horizontal and vertical bars of the inside reinforcing layer. The bars on the interior side of the plate, which of course are not in concrete at all should run across the shorter span of the wall. The usual precautions must be taken in

anchoring these bars. They may be hooked over horizontal bars in floor and roof, or bent to run horizontally for a length not less than 72 diameters, but it is essential that if the latter course is taken they should pass below the longitudinal reinforcing in the floor (or above that in the roof) so as to prevent them pulling out of the surface. In a multi-storey building, the vertical reinforcing should be made continuous in the whole height either by welding or hooking successive lengths together. The scabbing plate cannot usually be adequately tied at its edges, and so no allowance should be made for it in computing the percentage steel in the wall.

(iv) Other methods of retaining the scabbing plate. Various other devices have been suggested for retaining the soffit plate in position on the interior surface on the concrete. One such consists in passing ties round the reinforcing in the body of the concrete, and welding them to the surface of the plate. It has been suggested that these ties should be provided at a rate of 0.3 sq.in. per sq.ft. area. In the view of the writer such methods do not really afford an adequate solution of the problem. In at least one case they have been proved experimentally to be ineffective.

(d) The support of concrete during pouring. It will readily be appreciated that to pour a lift of perhaps 6 ft. in thickness over an area of roof having a minimum span perhaps 60 ft. at a height of 60 ft. above the ground, presents a considerable problem of structural engineering on its own account[¶]. The ordinary methods of support with timber or steel shuttering are quite inadequate in such a case. Undoubtedly the best solution is to extend the principle noted above of carrying the concrete on the plate and joists which will ultimately form the bottom surface of the roof. To carry the tremendous load involved in this case on ordinary joists would, however, involve the use of unnecessarily large members, and accordingly each joist is replaced by a steel truss, of total depth usually about two-thirds of the roof thickness. In the case of a roof of total thickness 12 ft. to be poured in two equal lifts, the trusses might be placed at three foot centres, and have depth 8 ft. The central bending moment per truss for span 60 ft. after the first pour is 1.18×10^6 lb.-ft., so that the tension in lower member at the centre is 1.475×10^5 lb. It is unnecessary to provide for any "factor of safety" in the trusses, or even to keep within the elastic limit, since this load occurs once only, and for a short time while the concrete is hardening. A working stress of 10 tons/sq. in. is therefore quite acceptable, and accordingly joists of 10" x $4\frac{1}{2}$ " x 25" are adequate. The top member of the joist must be laterally braced to prevent buckling, and the ordinary slab reinforcement can often be used for this purpose. The spalling plate, for which a light troughing can often be used to provide stiffness, is welded on to the lower flange of the bottom members in the usual way. In computing the percentage reinforcement required in the concrete, the steel in the lower members of the trusses can be taken into account, but not the remainder since it is very badly placed for most purposes. The first lift of concrete must of course be allowed to harden before the second is poured, and the whole reinforcing system must be more than sufficient to sustain the final static load due to the weight of the slab.

In some cases in fortifications having the lower surface of the roof at or near ground level, a heroic expedient has been adopted. The walls are first constructed in trenches of appropriate dimensions dug for the purpose. The lower-face steel and roof reinforcing are then placed in position and the whole roof is cast on the ground. After an appropriate interval to allow for hardening of concrete, the earth is then

¶ This was approximately the problem which faced the enemy during the construction of the Atlantic coast submarine pens.

excavated from under the roof slab, and finally when excavation has proceeded to the specified depth, the floor is placed in position. The floor in this type of structure is usually a light one, and floor damage is prevented by a burster slab forming an extension of the main roof. Where a semi-sunk or fully sunk construction is required, this method has much to recommend it, and, indeed, its simplicity is an argument in favour of the selection of semi-sunk forms of construction where a very high degree of protection with corresponding enormously heavy roofs is required. Of course, the condition of the site is always a dominating factor in such designs. The soil may be too hard to permit large-scale excavation, or alternatively too waterlogged to allow sunken construction.

(e) The repair of bomb-proof structures. Any structure, even the most massive is liable to bomb damage of more or less severity. If the design is completely successful, and the weapons used are no more powerful than those contemplated by the designer the damage will be restricted, in the case of direct hits, to surface craters with perhaps some slight bulging in the steel-work on the underside of the roof at the point struck, and in the case of a near miss, to cracking in the concrete in the walls with some bulging of the inner surface. In such cases an effective repair can be carried out simply by patching the exterior face with plain concrete.* If there is no bulging on the inside face such a repair will practically restore the original strength. If some bulging has taken place, the status quo cannot quite be restored, but a compensating strength can be achieved by increasing the thickness over the damage span with an additional layer of concrete. If the original static strength (in the case of a roof) was insufficient to sustain the additional weight, then additional support must be provided in the interior in the manner described below.

If severe damage has been done, if the roof or walls are holed or very badly bulged, it must be assumed (indeed it will probably be obvious) that some of the inner-face steelwork has been effectively destroyed. To restore it exactly will necessitate cutting out the original members - a lengthy operation if they are, as they should be, well embedded in concrete at their ends. A much easier method is simply to cut away the loose ends of the original inner-face steelwork, and erect a new frame consisting of steel members supported at their ends either on concrete posts, or on continuous steel stanchions. Having thus provided the necessary support on the inside face, the hole or bulge can be patched with concrete on the outside as before. If an open hole is being repaired, it can be seen whether the reinforcing bars in the interior of the concrete have or have not been cut. If they have, the loose ends can be straightened and welded together to provide the necessary reinforcement for the new concrete. If they are still intact, the fact that they are somewhat distorted is probably of no consequence. When the bomb has not blown an open hole, but has caused a severe bulge, it can usually be assumed that the reinforcing bars in the solid have not been cut, unless the concrete is so badly shattered that it can easily be removed, leaving an open hole.

We have now touched on most of the main points which arise in the design of heavy shelters and fortifications. We devote the few pages remaining in the chapter to more detailed consideration of three individual designs, differing widely in size and strength.

9.10 Commentary on three existing designs

(a) The original "bomb-resisting" shelter ¹¹ One of the original "bomb-resisting" shelters designed in 1939 is shown in Figs. 9.5a and 9.5b. At this time practically none of the experimental work described in this book had been carried out, and the designers had only the most fragmentary information on which to proceed. How would more modern information modify their plan?

First, with regard to the dimensions of the structure as a whole, it will be noticed that the roof thickness exceeds that of the walls above ground level. That is to say, the roof would only be perforated by a bomb larger than that which, exploding sideways-on in contact would blow a hole in the walls. This, of course, is a perfectly logical and correct design. Not only is the chance of a direct hit much larger than the chance of a near-miss so exactly placed as to give the effect of sideways-on contact, but the consequences of perforation are far more serious than those of any external explosion, even one capable of blowing a hole in the wall. In the former

* Loose pieces of concrete must be removed from the crater before the new patch is poured.

case all the occupants of the shelter will be exposed to severe risk, in the latter case only those near the hole, who are likely to be struck by flying pieces of concrete, are in much danger. Three out of the four compartments will probably be safe. Thus it is the perforation that must be countered as a first priority. The wall thickness below ground level is made consistent with that above ground level; again a quite sound procedure, although the probability of an effective contact shot is perhaps a little higher than above the surface since the attitude of the bomb is less important. When they came to the floor, however, the designers did not continue with the policy of providing less protection against unlikely events than against probable ones. They realized that for equal resistance to explosion, floor and sub-surface walls must be equally thick and they designed accordingly. But a contact shot below the floor is definitely more improbable than one against the walls, and so a logical policy would reduce the thickness there. Probably a modern design would show a floor thickness reduced to about 3 ft. 6 in. The increased wall thickness required below the surface would probably be placed outside rather than inside the above-ground walls in order to secure increased internal volume with only a small additional consumption of material.

When we come to the reinforcing diagram, Fig. 9.5b, we see that ideas have changed rather fundamentally. Except for some additions on the under-side of the roof, the steel is roughly uniformly distributed between inner and outer faces, whereas the contemporary plan is to place the greater part of the steel on the inside, most of the remainder near the centre, and almost none at the outside. The idea of scabbing plates for walls, as well as roof is comparatively recent, and we have already stated that we consider the means adopted here for anchoring the roof scabbing plate (by vertical links) to be inadequate.

(b) A German "Bunker" shelter¹² In Fig. 9.6a is shown a plan and section of one of the large "Bunker" shelters built by the Germans in the years 1941-43. The one shown is one of the most recent, and was in fact left unfinished in 1944. The idea that roof and above-ground walls should be of the same thickness, has been adopted, though, as we saw above, it is very questionable whether this arrangement is in fact the best. The intention has apparently been to provide complete protection against the 1000 lb. bomb, and to neglect the risk that a larger penetrating bomb might be used, and it is arguable that the policy was justified by events - very few delay-fuzed bombs larger than 1000 lb. were in fact dropped on Germany.

A much more serious error has however been made in the internal design of the shelter. Only the roof, walls and outside wall footings have been reinforced. Internal walls have been constructed of mass concrete or brick. Even a quite small internal explosion, or a large external explosion near the door might be sufficient not only to demolish such walls, but to convert them into most dangerous missiles which could not fail to cause many casualties. The percentage reinforcing necessary to prevent this disintegration is as we have seen very small, not more than 0.06 per cent, but its presence is essential in almost all construction for protective purposes.

In Fig. 9.6b we show the wall reinforcing arrangement which we have already instanced as being one of the best that has been devised. True, the writer would prefer to omit the concrete cover on the inside face, and to replace the close mesh of small bars shown in the diagram by continuous strips of sheet steel passed through the large U-frames, with narrower pieces welded on to close the gaps between frames. It may seem that this change is difficult to carry out, and that it does not provide any large increment in safety. The reply may be made that since the arrangement avoids the use of internal shuttering it will not on balance lead to an increase of labour requirement. Further, we may remark that a piece of the internal cover concrete, say 1 ft. square and 2 in. thick weighing 2 lb. does not have to travel very fast to cause a serious injury.

(c) A typical "very heavy" fortification¹³ Fig. 9.7 shows the immense concrete fortification constructed by the Germans at Siracourt in the Pas de Calais. This erection was of course cast on the ground, and the subsequent excavations were never completed. Its general shape was presumably laid down from considerations of the purpose for which it was required; apparently a chamber about 14 ft. high 50 ft. wide and 600 ft. long with a single large entry had to be made as nearly as possible bomb-proof[‡].

For this purpose, the general shape of the section can hardly be improved on. The burster and the short wedge-shaped walls make it very unlikely that a bomb will ever penetrate below the floor. The roof is, nominally at least, proof against the largest bomb at that time in our armoury - the 12,000 lb. M.C. known as "Tallboy". The transverse roof reinforcing was much as we have recommended, and there was a soffit plate supported on rolled steel joists in the manner of Fig. 9.4a. Yet this structure was attacked and so seriously damaged that the whole project was abandoned.

The roof plan in the diagram shows how this happened. The designer had made two errors, one slight, the other serious, and, with remarkable consistency, the two bombs shown on the plan exploited these errors to cause damage, one slight and the other serious. Let us consider first the near-miss shown on the top edge of the plan. This near-miss destroyed a length of burster, but this was of course, of no consequence, since the burster is there for that purpose. The designer had realized that it was necessary to use a "unit construction" to make a joint between the burster and the main structure which would enable the former to move freely without damaging the latter. Instead of carrying out this plan logically however, he allowed the roof to lap a few feet over the burster, as shown in the section, and thus he prevented free relative movement. The near-miss bomb, therefore not only broke up the burster slab but also caused a complicated system of cracks to spread through the main roof from the point where the burster lifted it. The error here was slight - a mere matter of stepping the joint between roof and burster instead of leaving it plain, and the damage also was not very serious.

In designing the roof slab, however, undue attention was given to the problem of contraction. Every few yards along the length of the building there was a completely discontinuous butt joint through which no reinforcing bars were passed, and in which a layer of precast blocks were placed, presumably with a view to allowing free relative movement of adjacent sections. The direct hit indicated on the plan fell exactly on one such joint, penetrated some distance and in its explosion caused very serious damage, which if the excavation had been complete at the point, would probably have amounted to collapse, over the two portions of the roof between which it struck. Had longitudinal continuity been maintained, the damage would have been much less severe both because the absence of the joint would have reduced the penetration of the bomb and because the damaged portions would have received much greater support from their neighbours. True, some slight damage might have been transmitted to these adjacent portions had the roof been continuous. But for the proper working of the building it was essential that the whole length should be intact. To adopt a construction which made it easy to put the whole out of action by destroying a single section was therefore, as the event proved, totally incorrect.

[‡] There is reason to believe that the designer had especially in mind attack by the British 2000 lb. armour-piercing bomb. He was not informed as to the development of a larger missile - Tallboy.

TABLE 9.1

CONTACT EXPLOSIONS ON CONCRETE - FULL-SCALE TESTS IN AIR

Bomb	Charge-weight of bomb W lb.	Thickness of slab t (in.)	Reinforcement	Scabbing plate	$t/W^{1/3}$	Damage
50 kg. S.C.4 (side-on)	55 TNT	24	0.7% two-thirds within 1 ft. of inner face	No	6.3	Slab completely perforated, forming hole 3 ft. in diameter.
500 kg. S.C.5 (side-on)	500 lb. (Approx.) TNT	72	1% two-thirds within 1 ft. of inner face	Yes	9.1	Surface crater 11 ft. diam. x 2 ft. in deep concrete through the whole thickness, shattered, but retained on reinforcing in rear surface. Bulge at rear 31 in. on a clear span of 18 ft. Soffit plate displaced.
50 kg. S.C.5 (side-on)	55 lb. TNT	39	0.38% two-thirds near inner face	No	10.2	Surface crater 4 ft. diam. x 9 in. deep. Concrete on the rear face behind inner reinforcing layer scabbed off over area 9 ft. x 6 ft. Permanent deflection of reinforcing 3 in. on 6 ft. span.
Bomb replica4 (cased charge) side-on	1 1/2 oz. PE #	3	0.66% five-eighths near inner face	No	6.3	Slab completely perforated, forming hole 5" in diameter.
Bomb replica4 (cased charge) side-on	1 1/2 oz. PE	3 1/4	0.53% five-eighths near inner face	No	7.8	Surface crater 6 in. diameter x 1 in. deep. Very heavy scabbing at rear. The rear reinforcing failed to retain the shattered concrete in a volume 5" diameter x 2" deep, and a much larger area was shattered, but retained.
Bomb replica4 (cased charge) side-on	1 1/4 oz. PE	4 1/8	0.49% five-eighths near inner face	No	8.6	Surface crater 6 in. diameter x 1 in. deep. Very heavy scabbing at rear. Rear reinforcing failed to retain concrete in a volume 3" diameter x 1" deep, and a much larger area was shattered, but retained.

For a note on the use of this explosive in small-scale tests, see Chapter VI.

REFERENCES

1. Road Research Laboratory "Bomb-proof shelter design: Model experiments on the resistance to explosions of roof and walls recommended in A.R.P. Handbook No. 5A" ARP/324/LGS (= R.C. 327), February, 1942.
2. Road Research Laboratory "Relation between concrete strength and crater produced in unreinforced concrete slabs by cylindrical charges" MOS/407/RK: AC 7228 October, 1944.
3. Keretsinger, D.G. "Contact explosions on concrete" Interim Report No. 29 to Chief of Engineers, U.S. Army Committee on Fortification Design, June, 1944.
4. Road Research Laboratory "Model ($\frac{1}{8}$ th scale) and full-scale tests of resistance of reinforced concrete to attack by bombs nearby and in contact" ARP/376/LGS (= R.C. 358). September, 1942.
5. R. & E. Department "Report on bombing trials on a 6 ft. thick reinforced concrete target at Ashley Walk carried out on 12th, 13th, 16th and 17th May, 1943" R.C. 392, August, 1943.
6. R. & E. Department "Report on trials at Richmond Park with buried 50 kg. S.C. 250 lb. A.S., and 250 kg. S.C. bombs exploded in contact with underground reinforced concrete walls" R.C. 413, April, 1944.
7. Committee on Fortification Design "Report on resistance of reinforced concrete fortification type structures to explosions in direct contact (Camp Gruber)" Report to Chief of Engineers U.S. Army No. 26. AC 6524, June, 1944.
8. Walley, F. "Vulnerability of floors of surface and semi-sunk shelters and field-defence structures" R. & E. Department R.C. 414, April, 1944.
9. Walley F. and Whittaker, F. "The design of bombproof structures" R. & E. Department R.C. B9 Item 4, August, 1942.
10. R. & E. Department "The design of bombproof structures", Bulletin A.6. January, 1943.
11. Home Office, A.R.P. Department "Bomb resisting shelters" Handbook 5A, 1939.
12. Burn, D.C. & Christopherson, D.G. "Report on the Aachen air raid shelters" R. & E. Department R.C. 436, April, 1945.
13. Burn, D.C. et al. "Report on heavy concrete structures at Siracourt, Marquise-Mimoyecques, Wizernes and Watten including tunnels at Marquise-Mimoyecques and Wizernes, with particular reference to effects of air attack by Tallboy (M) R. & E. Department R.C. 437, April, 1945.







FIG 9-1 ZONES OF DAMAGE



Case 1 (Surface)




Case 2 (Surface)



Case 3 (Semi-sunk)

Note:- All dimensions are in feet.



Case 4. (Sunk)

Diagrams of Shelters

FIG: 9.2




FIG. 9.3.




FIG. 9.4. b.




FIG. 9.4. c.




FIG. 9.4. d.




FIG. 9.5A.

RECTANGULAR SHELTER FOR 200 PERSONS









FIG. 9.5B.


DETAILS OF REINFORCEMENT



-  BRICKWORK
-  MASS CONCRETE
-  REINFORCED CONCRETE

0 2 4 6 8 10 20 30
SCALE OF FEET

FIG. 96a
AACHEN.
HOHENZOLLERNPLATZ.
SHELTER No. 20.




FRAMES SPACED AT 19 1/2" CENTRES ALONG THE WALL.

HORIZONTAL & VERTICAL MESH OF No. 8 BARS AT 2" SPACING ON INNER FACE ONLY.

CONCRETE COVER ON INSIDE ABOUT 2 INCHES, ON OUTSIDE ABOUT 12 INCHES.

NOTE - ALL JOINTS WIRED - NO WELDING.

FIG. 96b WALL REINFORCING · HOHENZOLLERNPLATZ · (SHELTER NO. 20.)



ROOF PLAN






FIG. 9.7

N
1467

HO 225/ 72

CLOSED UNTIL


~~SECRET~~

Declassified Dec 19 88
J. E. Costello

SECRET

H0225/72

CD/SA(R)5

U.K. EYES ONLY

COPY NO. 16

HOME OFFICE

SCIENTIFIC ADVISERS' BRANCH

CO/SA 72

Casualty Estimates for ground burst
10 Megaton bombs

AUTHOR: EDWARD LEADER-WILLIAMS, 1 OCTOBER 1956

Summary

1956

Tentative estimates of casualties from up to 45 ground burst 10 megaton bombs on British cities are estimated for various conditions of shelter and evacuation.

Casualties from an attack aimed in the optimum way (to cause casualties) when there is no shelter or evacuation are found to range from over 2½ million killed by a single bomb to just over half a million per bomb by 45 bombs. The total evacuation of the evacuation areas shown in Fig. 8 is found to reduce fatal casualties from this attack by from 99 to 84% depending on the number of bombs. Similarly the evacuation of the priority classes (45%) combined with the provision of a high standard of shelter for the remaining inhabitants of the evacuation areas would reduce fatal casualties from this attack by from 99 to 86% depending on the number of bombs. These are the maximum savings that could result from these policies. If the enemy adjusted his attack so that all his bombs were aimed at reception areas, thus achieving the maximum casualties among the evacuated and/or sheltered population, the reduction in fatal casualties would range from 62 to 44% for the policy of 100% evacuation, and from 79 to 65% for the policy of 45% evacuation combined with shelter. In the event of either of these policies being adopted the enemy would probably make some adjustments in his attack without going as far as in the limiting case above of aiming all his bombs at reception areas. The saving in casualties would then be intermediate between the two sets of figures given above.

3. The shape and size of the fall-out pattern. The size and shape of the fall-out pattern for a ground burst 10 megaton bomb has been determined from the data presented at the February 1954 Tripartite conference*. The pattern consists of an ellipse with one apex at ground zero together with a circle centred a short distance down wind of ground zero. This pattern is reproduced as Figure 1 and the principal dimensions of some of its contours are shown in Table 1.

* 15-19 Feb. 1954, "Tripartite Conference: Effects of Atomic Weapons on Human Beings and their Environment", Washington D.C., AFSWP & USAEC

TABLE 1

Secret Principal dimensions of fall-out pattern from ground-burst
10 megaton bomb with a 15 knot wind

Dose rate (r/hr at 1 hour)	Down wind length of ellipse (miles)	Cross wind width of ellipse (miles)	Radius of ground zero circle (miles)	Down wind displacement of ground zero circle (miles)
5000	23	5.5	2.6	1.5
3000	33	7	3.1	1.7
2000	45	8	3.6	1.9
1000	72	11	4.5	2.3
500	115	16	5.7	2.6
300	160	22	6.8	2.8

Note: these data are from 1951 Jangle-S (1.2 kt) for downwind areas and 1952 Ivy-M (10.4 Mt) for upwind and crosswind of ground zero, with both distances and dose rates scaled by the cube-root of total yield (USNRDL-TR-1). This was incorporated into the June 1957 Effects of Nuclear Weapons edited by Glasstone. 1956 Redwing data showed upwind dose rates had been exaggerated 10-fold.

houses with windows blocked the best data available are those from Guildford (CD/SA/75) and for the present study it will be assumed that the proportions of houses having different protective factors is the same for the whole country as it was found to be for Guildford. For purposes of computation the actual range of protective factors found at Guildford may be approximated as shown in Table 2.

TABLE 2

Protective factors of Guildford houses

Undamaged houses with windows blocked.

Percentage of houses	Protective factor
15	150
10	70
55	30
20	10

7. Effect of Blast Damage on protective factors. Consider a ground floor room of a typical 2 storey terraced house with 9 in. brick walls. This is found by the method of CD/SA.68 to have a protective factor (windows blocked) of 38. In experiments carried out at the Fuel Research Station* on the penetration of particles from a power station chimney (simulating fall-out) into a room with an open window, it was found that the average concentration inside the room was 14% of that outside.

8. If, due to blast damage of Category D to the house, all windows other than those of the refuge room are broken, then it will be assumed that 14% of the outside concentration of fall-out will get onto the first floor and into the ground floor room alongside the refuge room. This will reduce the protective factor of the refuge room to 23. The principal additional effect of C damage will be to let much of the contamination which would have lodged on the roof, through to the first floor. If it is assumed that the concentration on the roof and on the first floor is 50% of that outside and, as before, that 14% gets into the room alongside the refuge, then the protective factor falls to 14. For B damage the most realistic assumption seems to be 100% of the outside concentration on the first floor and 14% in the refuge room itself and in the room alongside. The protective factor is then 7.

9. Applying similar reasoning to the above to a basement under a 2 storey house, and to a 2 storey detached house we get the results summarised in Table 3.

* D.S.I.R. Fuel Research Station Report Ref. D.F.R. 47/10/(a)
"Measurement of Dust Deposition in a Room with an Open Window".

/ TABLE 3

TABLE 3

Protective factors of damaged houses

Location of refuge room	Protective Factor			
	Undamaged	D damaged	C damaged	B damaged
Ground floor of 2 storey detached house	14	11	9	5
Ground floor of 2 storey terraced house	38	23	14	7
Basement under 2 storey house	150	38	30	10

10. The reductions in protective factors due to damage must now be applied to the range of protective factors shown in Table 2; the results of this are given in Table 4 which will provide the basis for estimating fall-out casualties in damaged houses.

TABLE 4

Assumed Percentages of damaged and undamaged
houses having different protective factors

Percentage of houses	Protective Factor for damage category:-			
	Undamaged	D damaged	C damaged	B damaged
15	150	38	30	10
10	70	30	20	8
55	30	19	13	6
20	10	8	6	3

11. Stay in, and transit from a fall-out area. It will be realised from the Appendix that the length of time people stay in a fall-out area and their speed of transit when they leave it, vitally affect their total dose. Moreover their optimum time of stay is influenced by such factors as the surviving protection of their house, and their position in the fall-out pattern - factors which can certainly not be known by individuals in the fall-out area.

12. However for the purposes of calculating fall-out casualties some assumptions must be made, and those made for this study are summarised in Table 5.

/TABLE 5

TABLE 5

Assumed times of arrival of fall-out, durations of stay and speeds of transit

Category of house damage	Time after burst of arrival of fall-out (T_1)	Duration of stay in refuge (T_2)	Speed of transit out of contaminated area (v)
Undamaged	2 hours	48 hours ⁽¹⁾	20 miles/hr ⁽¹⁾
D damage	$\frac{1}{2}$ hour	48 hours ⁽²⁾	20 miles/hr ⁽²⁾
C damage	$\frac{1}{4}$ hour	Optimum ⁽⁴⁾ given by equation (2) of the Appendix. Actual range from 5 to 24 hours depending on protective factor of house.	2 miles/hr ⁽³⁾
B damage	$\frac{1}{4}$ hour	Optimum ⁽⁴⁾ given by equation (2). Actual range from $2\frac{1}{2}$ to 9 hours.	2 miles/hr ⁽³⁾

Notes of Table 5.

- (1) In accordance with the proposals of the Provisional Scheme of Public Control in the fall-out area that the occupants of Zone Z should be evacuated by mechanical transport, starting 48 hours after the burst.
- (2) There seems no reason why the above scheme should not operate in a D damaged area.
- (3) Mechanical transport will probably not be able to penetrate into C and B damaged areas affected by heavy fall-out, and therefore transit on foot at 2 miles per hour is assumed.
- (4) In practice these people might quit before the optimum time, or they might stay for the recommended 48 hours. In either case they would increase their dose. However leaving at the optimum time has been assumed for the present study since it leads to minimum casualties and ensures that the value of shelters will not be overestimated when casualties with and without shelters are compared.

13. Dose rate contours for death and sickness. The 50% lethal dose has been taken as 500 r and the 50% sickness dose as 200 r and it has been assumed that the number of people who survive a higher dose is equal to the number who die from a lower; that is to say it has been assumed that everyone who receives 500 r or more dies and everyone who receives less survives. This

/assumption

SECRET

U.K. EYES ONLY

IDEALIZED LOCAL CONTOURS
FOR RESIDUAL RADIATION






FIG. I

EVACUATION AND NEUTRAL AREAS
(AS PROPOSED BY THE CDJPS WORKING PARTY ON EVACUATION)

- Areas of Highest Risk
- Evacuation Areas
- Neutral Areas



SECRET U.K. EYES ONLY
TOTAL CASUALTIES FOR DIFFERENT EVACUATION POLICIES




FIG. 9

SECRET - U.K. EYES ONLY

TABLE 1

Casualties with shelter and no evacuation(Aiming points chosen to maximise
blast casualties with no evacuation or shelter)

Bomb No.	Aiming Point	Cumulative Total (1000's)	
		Killed	Seriously Injured
1	London (1)	100	0
110 2	London (2)	210	0
55 3	London (3)	265	15
30 4	London (4)	295	15
160 5	Glasgow (1)	455	30
95 6	Manchester (1)	550	40
90 7	Birmingham (1)	640	50
105 8	Liverpool (1)	745	50
70 9	Tyne (1)	815	50
30 10	Birmingham (2)	845	75
130 11	Sheffield (1)	975	105
70 12	West Riding (1)	1,045	125
95 13	Bristol (1)	1,140	160
15 14	Birmingham (3)	1,155	175
125 15	Edinburgh (1)	1,280	195
10 16	Manchester (2)	1,290	230
20 17	Manchester (3)	1,310	250
10 18	London (5)	1,350	255
30 19	London (6)	1,380	275
75 20	Nottingham (1)	1,455	280
21	London (7)	1,520	305
22	London (8)	1,585	330
23	Glasgow (2)	1,510 X	335
24	Tyne (2)	1,460 X	335
25	West Riding (2)	1,520	335
26	Stoke on Trent (1)	1,770	395
27	Hull (1)	1,845	400
28	Leicester (1)	1,945	415
29	Portsmouth (1)	2,045	435
30	Tees (1)	2,140	440
31	West Riding (3)	2,235	480
32	Coventry (1)	2,340	485
33	Cardiff (1)	2,395	495
34	London (9)	2,420	510
35	Liverpool (2)	2,415 X	510
55 36	West Riding (4)	2,470	555
37	London (10)	2,540	605
38	Brighton (1)	2,790	685
39	Blackburn (1)	3,025	710
90 40	Plymouth (1)	3,115	720
41	Wigan/St. Helens (1)	3,135	725
42	Bournemouth/Poole (1)	3,365	765
43	Southampton (1)	3,420	770
44	Blackpool (1)	3,580	895
45 45	Sheffield (2)	3,625	910

TABLE 2

Casualties with shelter and no evacuation(Aiming points chosen to maximise casualties under these conditions)

Bomb No.	Aiming Point	Cumulative total 1000's	
		Killed	Seriously Injured
1	Stoke on Trent, Newcastle-under-Lyne	250	80
2	Brighton, Hove	500	150
3	Bournemouth, Poole	730	175
4	Aberdeen	920	190
5	Blackburn, Accrington, Oswaldthistle	1,155	255
6	Dundee, Tayport, Newport, Monifieth	1,345	260
7	Blackpool, Lytham St. Annes, Cleveleys	1,525	430
8	Southend	1,680	440
9	Preston, Fulwood, Walton-le-Dale	1,815	340
10	Glasgow	1,975	360
11	Rhondda, Merthyr Tydfil, Pontypool (1)	2,145	490
12	Burnley, Nelson, Colne	2,265	560
13	Swansea, Neath, Port Talbot	2,445	655
14	Norwich	2,595	700
15	Mansfield, Sutton (Kirkby) in Ashfield	2,730	740
16	Reading	2,910	795
17	Luton	3,080	820
18	Watford, St. Albans, Hemel Hempstead	3,190	890
19	Northampton	3,315	910
20	York	3,435	920
21	Oxford	3,565	930
22	Ipswich	3,680	940
23	Liverpool	3,785	940
24	Farnborough, Aldershot	3,935	990
25	Gloucester, Cheltenham	4,000	1,040
26	Maidstone, Chatham, Rochester, Gillingham ...	4,065	1,105
27	Slough, Windsor, Maidenhead	4,215	1,145
28	London (1)	4,315	1,145
29	London (2)	4,415	1,145
30	Bath	4,545	1,165
31	Margate, Broadstairs, Ramsgate	4,630	1,175
32	Egham, Staines, Chertsey	4,740	1,180
33	Darlington	4,840	1,190
34	Lancaster, Morecambe, Heysham	4,905	1,220
35	Edinburgh	5,030	1,245
36	Cambridge	5,125	1,250
37	Birmingham	5,215	1,265
38	Worthing, Littlehampton	5,320	1,260
39	Swindon	5,405	1,270
40	Leicester	5,505	1,280
41	Burton on Trent, Swadlincote	5,620	1,345
42	Rhondda, Merthyr Tydfil, Pontypool (2)	5,750	1,375
43	Bishop Auckland, Durham, Shildon	5,855	1,405
44	Easington, Seaham, Hatton	5,915	1,410
45	Torquay, Teignmouth, Paignton	5,970	1,430

TABLE 3

Saving in fatal casualties with various shelter and evacuation policies (attack on centres of population)

No. of Bombs	Percentage saving in killed			
	45% evacuation	100% evacuation	45% evacuation and shelter	No evacuation and shelter
5	44	98	96	94
10	44	98	96	93
15	44	95	94	91
20	44	94	94	92
30	43	90	91	90
40	40	84	88	87


TABLE 4

Saving in fatal casualties with various shelter and evacuation policies (worst possible attack)

No. of Bombs	Percentage saving in killed		
	100% evacuation	45% evacuation and shelter	No evacuation and shelter
5	62	79	85
10	58	76	84
15	52	72	81
20	50	71	80
30	47	68	78
40	44	65	77

Fig. 86 Construction and installation drawings 1982 Anderson shelter
for outdoor kit shelter design.

(Domestic Nuclear Shelters - Technical Guidance)



IMPORTANT - SHELTER SHOULD STAND ON, AND BE COVERED BY EXPANDITE PROOFEX No12 OR SIMILAR MATERIAL.

Fig. 92

UK Government 1982 Anderson

Concrete Slab 150m.m. thick with
One layer of mesh B.S. ref. A.142
placed centrally

1000 m.m. Minimum Earth Cover
Stiffen Surface with : Rockery or Grass / Roots
Stones or Concrete.

Polythene or Cloth layer.


150 m.m. Crushable material

Earth Backfill, firmly compacted.

Line of Excavation.

Undisturbed Soil

Original Ground Level



(Domestic Nuclear Shelters - Technical Guidance)

20 m.m. Plywood Base Slab.

Line of Basic Shelter

'Proofex N° 12' or similar material

'Expandite Proofex N° 12.' or similar material

applied to bottom of plywood and
turned up to lap with shelter.

applied to the entire exterior of the shelter.

TYPICAL CROSS SECTION : (FLAT BOTTOM)

ANGLO-GERMAN WORLD WAR II ESCALATION

<i>Phase</i>	<i>German Actions</i>	<i>British Actions</i>
“Phony war” (September 1, 1939– May 9, 1940)	Central sanctuary “observed” Tactical symbolic attacks	Central sanctuary “observed” Tactical symbolic attacks
Poland and Norway	Tactical bombing with avoidance	
Defeat of France	A noncentral exemplary attack Counterforce with avoidance	Strategic with avoidance
Air-superiority battle	Counterforce with avoidance Limited strategic with avoidance	Strategic with avoidance
Aerial blitz (1940)		
a. August 24–September 6	Strategic with avoidance	Exemplary reprisal plus Strategic
b. September 7–October 29	Strategic	Augmented strategic
c. October 31–December 11	Strategic	Countervalue
d. December 11 on	Strategic	
Lull	Precise reprisals	Experiments
One-sided eruption		
a. 1942	Exemplary reprisals (“Baedeker raids”)	Selective . . .
b. 1943–45	Countervalue devastation and ex- emplary reprisals	Countervalue devastation, strate- gic and counterforce

ARCHIVES
CGSC FT LEAVENWORTH, KAN

CONFIDENTIAL MODIFIED HANDLING AUTHORIZED
MONOGRAPH

SEP 16 1954

UNCLASSIFIED

ACCESSION NO _____
O REGISTRY _____

THE EMPLOYMENT OF V-WEAPONS BY THE GERMANS DURING WORLD WAR II

DOWNGRADED AT 2 YEAR INTERVALS;
DECLASSIFIED AFTER 12 YEARS.
DOD DIR 5200.10

BY

LIEUT. COLONEL M.C. HELFERS, Jr



CONFIDENTIAL MODIFIED HANDLING AUTHORIZED

DRAFT

UNCLASSIFIED

OFFICE OF THE CHIEF OF MILITARY HISTORY
DEPARTMENT OF THE ARMY

CONFIDENTIAL MODIFIED HANDLING AUTHORIZED

UNCLASSIFIED

MAPS

Facing Page

1. Operational Planning for the Commitment of V-1's from Germany by LXV Corps (Early October 1944).....	40
2. V-1 Operational Areas (Mid-October 1944).....	42
3. Proposed V-2 Lay-Out in Northern France.....	58
4. V-2 Operational Command Set-Up (Sep 1944 - Mar 1945).....	70
5. V-2 Operations (1 Sep 1944 - 1 Oct 1944).....	72
6. Situation Map: 901st Artillery Regiment z.V. (Mtz.) (March 1945).....	82


ILLUSTRATIONS

Placing V-1 on Launching Dolly.....	30
Preparing V-2 for Launching.....	66
V-2 Ready for Launching.....	74
V-1 Crater and Damage, London, 9 August 1944.....	92
V-2 Crater and Damage, Antwerp, 28 December 1944.....	94

UNCLASSIFIED

UNCLASSIFIED


Chart I



THE V-WEAPON FIELD COMMAND

UNCLASSIFIED

UNCLASSIFIED



PREPARING V-2 FOR LAUNCHING (Captured Photograph)

UNCLASSIFIED



HOME OFFICE

CIVIL DEFENCE

RESTRICTED

The information given in this document is not to be communicated, either directly or indirectly, to the Press or to any person not authorised to receive it.

General Instructor's Notes

January 1953

AG 5

Advanced General Training
REFUGEE ROOM

Notes for Instructor

1. This lecture and practice on the selection and protection of a Refugee Room is given to the General Instructor as a guide should he at any time be called upon to give this instruction.

2. Instructor will find following home-made visual aids useful for lectures.

(a) Pictorial diagram of interior of typical refuge room.

(b) Model window and frame, with net curtains pasted on.

(c) Model window and frame, with a small mesh wire netting (mesh not larger than half an inch) fastened to frame.

(d) Model window and frame, with lightweight wooden shutter (a type giving a "push fit" into window frame) with stout rubber anchorages top and bottom.

3. For the practice which follows the lecture, the use of a house, preferably basement type, is required. The Instructor should make a preliminary survey so that he is familiar with any peculiar features.

Object of Lecture and Practice

4. To study the principles governing the selection and protection of a refuge room in an ordinary house, and to practise the selection of such a room.

Selection and Protection of Room

5. Refuge room next best thing to approved type of shelter. Cupboard under stairs very popular 1939/45. Use of refuge room for sick people, babies and small children during night, better than going out in bad weather.

6. Main Points for Consideration: Intended to give shelter from blast and splinters, not direct hit. Must have separate entrance and exit. All round thickness of walls of 13½ inches of brickwork or its equivalent. Basement room very good, ground floor next.

SC 8

Morrison Shelter

3. Holds two adults and one child (or two very small children). Suitable for the two-storey house, and will stand up to collapse of whole of such house. Must be placed on solid floor without any room or cellar below it. Steel mesh sides to protect the shelterers from flying debris should the protecting walls be blown in.

Protection against Blast and Splinters

4. Trench Shelter: 1939/45 war type. Roofed. Concrete lined or with alternative revetment of timber, corrugated iron, filled sandbags, wire mesh or expanded metal. Experience during the war proved that in order to prevent the collapse by earth shock, the roof, floor and all walls must be adequately tied together as a continuous structural unit. (Note that a top cover of 3 feet of earth, or its equivalent, will convert shelter to Grade A standard.)

5. Brick Surface Shelter: Early 1939/45 war type with walls of 13½-inch unreinforced brickwork.

6. Refuge Room: In building with walls of 9-inch thick unreinforced brickwork, to which has been added an outside skin of 4½ inches of unreinforced brickwork or 5 inches of unreinforced concrete up to a minimum height of 6 feet above floor level. An alternative skin is 10 inches of earth behind shuttering. Windows, and any outside door bricked or concreted up to same height and equivalent thickness. Windows, where gap has been left at top to admit daylight, provided with anti-shatter protection. Ceiling joists, supported by adequately braced posts to give added strength against possible debris load.

BG 8

Long Range Rocket

7. As used in latter part of 1939/45 war, was propelled by mixture of liquid oxygen and alcohol. Length 46 feet. Total weight with eight and a half tons of fuel was 12½ tons. Maximum speed 3,500 m.p.h. Maximum range 200 to 230 miles. Reached height of 50 to 60 miles on journey to England from Holland. Launched from transportable platform. Warhead about one ton.)

8. Area of material damage caused by rocket similar to that of flying bomb, although area of heavy damage slightly greater and area of light damage considerably less. Caused more casualties than flying bomb on account of surprise effect. No time for warning signals.

Unexploded Bombs

9. Unexploded missiles have considerable tactical value. To safeguard public, affected area is evacuated with consequent loss of industrial production. Ten per cent. of bombs on United Kingdom 1939/45 were UX. Quick detection essential. Reason for UX Missiles may be defective fuses or delayed action fuses. All UX missiles must be treated as delayed action, as no means of differentiating.

~~SECRET~~

[Redacted]

50X1-HUM

IRONBARK

CSDB-3/650,395

MINISTRY OF DEFENSE OF THE USSR

SECRET

Copy No. _____

**A GUIDE TO THE COMBAT CHARACTERISTICS
OF ATOMIC WEAPONS AND TO THE MEANS OF
ANTI-ATOMIC PROTECTION**

**Military Publishing House
Ministry of Defense of the USSR
Moscow -- 1957**

[Redacted]

-2-

~~SECRET~~

[Redacted]

[Redacted]

50X1-HUM

~~SECRET~~

50X1-HUM

IRONBARK

CSDB-3/650,395

The Guide to the Military Characteristics of Atomic Weapons and to the Means of Anti-Atomic Protection represents a revised and enlarged edition of the Short Guide, which was published in 1954. Contained herein are data on the destructive factors of an atomic burst and on the means of anti-atomic protection, and also some basic facts of atomic physics, which are necessary for a full understanding of the nature of an atomic burst and the particular destructive features of atomic weapons.

This Guide is intended as an aid to instructors and students of military academies, to instructors of advanced officer training courses and instructors of military schools, and also as guidance for those pursuing scientific research in the fields of atomic weapons and the development of means and methods of anti-atomic protection.

Comments on the Guide and suggestions for its improvement should be sent to the address of the Sixth Directorate of the Ministry of Defense.

Order No. 2187

-3-

~~SECRET~~

50X1-HUM

~~SECRET~~

50X1-HUM

CENTRAL INTELLIGENCE AGENCY
WASHINGTON 25, D. C.

18 JUN 1962

IRONBARK

MEMORANDUM FOR: The Director of Central Intelligence

SUBJECT : Table of Contents and Chapter VIII of SECRET
Soviet Manual on Atomic Weapons and Anti-
atomic Protection

1. Enclosed is a verbatim translation of the Table of Contents and Chapter VIII of a Soviet SECRET document titled "A Guide to the Combat Characteristics of Atomic Weapons and to the Means of Anti-atomic Protection". It was published in 1957 by the Ministry of Defense, USSR.

2. For convenience of reference by USIB agencies, the codeword IRONBARK has been assigned to this series of TOP SECRET CSDB reports containing documentary Soviet material. The word IRONBARK is classified CONFIDENTIAL and is to be used only among persons authorized to read and handle this material.

3. In the interests of protecting our source, IRONBARK should be handled on a need-to-know basis within your office. Requests for extra copies of this report or for utilization of any part of this document in any other form should be addressed to the originating office.




Richard Helms

50X1-HUM

Richard Helms
Deputy Director (Plans)

Enclosure

CSDB-3/650,395

Copy No. 

~~SECRET~~

50X1-HUM

~~SECRET~~

50X1-HUM

IRONBARK

CSDB-3/650,077

As is evident from the graph, approximately 5 seconds later, the intensity of gamma radiation reaching the earth's surface has decreased by a factor of hundreds. Even after ten seconds, however, the intensity of gamma radiation amounts to tens of roentgens per second. Therefore it is customary to consider that the time of action of gamma radiation on surface objects in medium-yield bursts is about 10 seconds. Where $t = 0.5$ to 1 sec, a sharp deceleration of the drop in radiation intensity takes place. This deceleration depends on the influence of the cavity of rarefied air (rarefied zone of the shock wave). Gamma rays pass through the rarefied air cavity almost without attenuation. The higher the yield of the burst, the greater the dimensions of the rarefied cavity and the sharper its influence on the ratio $I_\gamma = f(t)$. In high-yield explosions, a strongly pronounced maximum is even observed in the ratio $I_\gamma = f(t)$ corresponding to the time for passage through a given point of the shock wave compression zone.

Ten seconds after a burst the fission fragments of a single nucleus and the products of their decay emit on the average 3 to 4 gamma quanta. Hence it follows that in an atomic burst with a TNT equivalent of 30 kt, during which about 4×10^{24} nuclei fission, the total quantity of emitted gamma quanta amounts to

$$N_\gamma = 4 \times 10^{24} \times (3 \div 4) \approx 1.5 \times 10^{25} \text{ gamma quanta.}$$

The average energy of gamma quanta emitted by fission fragments is about 2 MEV. Therefore the energy carried off by gamma radiation is equal to $E = 2 \times 1.5 \times 10^{25} = 3 \times 10^{25} \text{ MEV} \approx 1.1 \times 10^{12} \text{ cal}$, i.e., it consists of about 4 percent of all the energy liberated by the burst.

The average gamma quanta energy emitted in the $N^{14}(n, \gamma)N^{15}$ reaction is equal to approximately 4 MEV, but their number is approximately equal to the gamma quanta emitted by fission fragments. However, the

50X1-HUM

-6-

~~SECRET~~

50X1-HUM

SECRET

50X1-HUM

IRONBARK

CSDB-3/650,077

Table 64
Values of the Doses of Gamma Radiation at Various
Distances from the Center of an Atomic Burst

Distance, in meters	Dose of gamma radiation, D_γ , in roentgens, for bursts of the following TNT equivalents.					
	8 kilotons		30 kilotons		150 kilotons	
	surface	air	surface	air	surface	air
200	~300000	~240000	---	---	---	---
300	83000	66000	---	---	---	---
400	31500	25000	200000	150000	---	---
500	13000	10400	83000	62000	~1000000	~700000
600	6300	5000	40000	30000	~500000	~340000
700	2900	2300	18000	13500	200000	135000
800	1600	1300	10000	7500	120000	82000
900	900	700	5500	4100	66000	45000
1000	460	370	3000	2250	36000	25000
1100	250	200	1600	1200	19000	13000
1200	140	110	900	680	10800	7400
1300	80	65	500	380	6000	4100
1400	45	35	300	220	3600	2500
1500	---	---	180	140	2200	1500
1600	---	---	100	75	1200	820
1700	---	---	60	45	700	480
1800	---	---	---	---	450	340
1900	---	---	---	---	260	180
2000	---	---	---	---	170	120
2100	---	---	---	---	100	70
2200	---	---	---	---	60	40

50X1-HUM

-9-

SECRET

**50% PROBABILITY OF SEVERE DAMAGE (COLLAPSE) FOR CITY BUILDINGS
(SOURCE: NORTHPROP, EM-1 NUCLEAR WEAPON EFFECTS HANDBOOK, 1996,
TABLE 15.6, AND FIGURES 15.10, 15.18, SURFACE BURSTS)**

	<u>BUILDING VALUES (NOMINAL)</u>			Peak overpressure	
	Oscillation Period (ms)	Static yield resistance (psi)	Ductility ratio (u)	20 KT (psi)	1MT
15.2.2, 3-8 Story Reinforced Concrete Building (Concrete Walls)	300	3.0	7.5	15	12
15.2.10, 3-10 Story Steel Frame Building	600	2.0	10	23	13

**THE ORIGINALLY
SECRET EM-1
SHOWS THAT
MODERN CITY
BUILDINGS
REQUIRE FAR
HIGHER PEAK
OVERPRESSURES,
EVEN AT
MEGATON
YIELDS,
THAN THE
WOODEN HOUSES
IN HIROSHIMA
FOR COLLAPSE**


OBSERVER

4 JULY 1982

**THIS MAN
THINKS YOU SHOULD BUY
A FALL-OUT SHELTER**

(One of his, preferably – he sells them. See page 24)







Blatchford factory-assembled shelters are made from 6in-8in thick precast reinforced concrete by BLATCON LTD of Midsomer Norton, Avon. Their managing director is John Blatchford (right). They can be built to accommodate between six and 14 people at a cost of about £1,000 per head, excluding installation. Ian Mathie of Blatcon claims a blast rating of at least one atmosphere and a PF of 2,500 when the shelter is buried 2ft beneath the surface, or 3,300 if, in addition, a 12in layer of reinforced concrete is poured around it.






NUCLEAR PROTECTION of Wellingborough, Northamptonshire, sell shelter equipment and supply the plans for a 12in thick reinforced concrete shelter. Tom Butler (left), who runs the firm, has raised his estimate of the shelter's PF, when buried under 40in of soil, from 2,000 to 5,000 using newly available Home Office tables, and claims a blast rating of one atmosphere. His shelter holds seven people and costs between £10,000 and £12,000.



OAKTREE EQUIPMENT LTD, of Faringdon, Oxfordshire, make the Crabtree Subterrain shelters, which are prefabricated galvanised corrugated steel cylinders with unusually long access ways, enabling burial up to a depth of 20ft. All the shelters in the range hold five to seven people in varying degrees of comfort, and prices range from £1,000 for the 7ft model to £9,660 for the 20ft model, plus installation. The steel walls are 0.1in thick and the designer, James Crabtree (above), claims a PF of 5,000 at a minimum depth of 4ft, and a blast rating of three atmospheres.

reinforced concrete shelter. Tom Butler (left), who runs the firm, has raised his estimate of the shelter's PF, when buried under 40in of soil, from 2,000 to 5,000 using newly available Home Office tables, and claims a blast rating of one atmosphere. His shelter holds seven people and costs between £10,000 and £12,000.



OAKTREE EQUIPMENT LTD, of Faringdon, Oxfordshire, make the Crabtree Subterranean shelters, which are prefabricated galvanised corrugated steel cylinders with unusually long access ways, enabling burial up to a depth of 20ft. All the shelters in the range hold five to seven people in varying degrees of comfort, and prices range from £1,000 for the 7ft model to £9,660 for the 20ft model, plus installation. The steel walls are 0.1in thick and the designer, James Crabtree (above), claims a PF of 5,000 at a minimum depth of 4ft, and a blast rating of three atmospheres.

2nd
EDITION

THE NUCLEAR SURVIVAL HAND- BOOK

LIVING THROUGH
AND AFTER
A NUCLEAR
ATTACK

BARRY POPKESS



THE NUCLEAR

THE NUCLEAR SURVIVAL HAND- BOOK

LIVING THROUGH
AND AFTER
A NUCLEAR
ATTACK

BARRY POPKESS



The most comprehensive
compilation of available
material.

THE NUCLEAR SURVIVAL HANDBOOK

If the West comes under nuclear or
chemical attack, many of us will survive.
For those who do, the nightmare may only
be beginning – for we are unprepared and
survival during and after the holocaust will
be largely a question of individual readiness
and planning.

This handbook is a highly detailed and
carefully compiled guide to what happens
in a nuclear attack, how to shelter, and how
to live afterwards.

With topics ranging from shelter
construction to foraging for food, it is at
once a practical handbook, a chilling
depiction of life after the war and a
devastating indictment of our lack of
preparation.

**SEE INSIDE FRONT COVER FOR
FULL CONTENTS.**

United Kingdom £1.75
Australia \$6.25*
*RECOMMENDED PRICE
Non-fiction 0-09-9724510-8

The most comprehensive
compilation of available material
- now revised and updated

THE NUCLEAR SURVIVAL HANDBOOK

If the West comes under nuclear or
chemical attack, many of us will survive.
For those who do, the nightmare may only
be starting – as survival during and after
the holocaust will be largely a question of
individual readiness and planning.


This handbook is a highly detailed and
carefully compiled guide to what happens
in a nuclear attack, how to shelter, and how
to live afterwards.

With topics ranging from shelter
construction to foraging for food, it is at
once a practical handbook, a chilling
depiction of life after the war and a
devastating indictment of our lack of
preparation.

**SEE INSIDE FRONT COVER FOR
FULL CONTENTS.**

Non-fiction
UK £4.95
Australia \$13.95*
Canada \$12.95*
*recommended price

ISBN 0-09-940110-X



9 780099 401100

THE NUCLEAR SURVIVAL HANDBOOK BARRY POPKISS

THE SURVIVAL GUIDE

- ☸ **Nuclear attack: what happens when the bomb drops; light, heat, blast and radiation.**
- ☸ **Chemical warfare: the alternative Armageddon; effects and precautions.**
- ☸ **Shelters: siting and construction.**
- ☸ **Biological hazards: with our health and sanitary services gone, man's old enemies can flourish, from smallpox to typhus; recognition and treatment.**
- ☸ **Vermis: prevention and extermination.**
- ☸ **Sustenance: how to store and decontaminate water; how to find nourishment from fungi, seaweeds and other plants; animal foods.**
- ☸ **The Social Survivor: civil disorder, self defence, life in devastated areas, contingency plans for administration and evacuation.**
- ☸ **Wounds and malnutrition: recognition and treatment.**
- ☸ **Appendices.**

NUCLEAR SURVIVAL HANDBOOK

Barry Popkess was born in 1929 in Farnborough where his father was Assistant Provost Marshal at Aldershot Command. During the nineteen thirties the family moved to Nottingham when his father was appointed Chief Constable. He joined the army at the age of seventeen as a trooper in the Royal Horse Guards and was commissioned into the 45th and 95th of Foot Sherwood Foresters with whom he served in the BAOR. After his army service he lived in Africa for some years.

His interest in civil defence stemmed initially from conversations with his father who had campaigned in the nineteen thirties for improvements in the defence of British cities against aerial attack. In 1957 he began to collect information for his own use, drawing on scientific, technical, medical, biological, botanical and legal sources. Twenty years later he began to turn his mass of information into *The Nuclear Survival Handbook*. He now lives in Southampton with his wife and three children.

Contents

List of Illustrations	8
Preface	9
Prologue	13
1 A Nuclear Explosion	15
Fireball; light; heat; blast; nuclear radiation; monitors; forms of radioactive energy; stages of radiation; effects of radiation on the body; refuge from initial radiation; refuge from fallout; decontamination; internal radiation; symptoms of radiation sickness; physiological precautions and treatment for radiation sickness; ultraviolet radiation	
2 Chemical Warfare	46
Chemical weapons; precautions; decontamination and treatment; gas masks; accidental dispersion of chemical poisons; post-holocaust smog	
3 Shelters	67
Siting a shelter; specifications for private shelters; conversion shelters; precautions against blast and fire; precautions against radiation; purpose-built shelters; intruders; size of shelter, its occupants and foodstock; equipment; water supply; materials and design; ventilation; lighting; precautions against electromagnetic pulse; deep shelters	
4 Biological Hazards	113
Precautions, symptoms and treatment: anthrax; botulism; brucellosis; cholera; diphtheria; dysentery; food poisoning; glanders; lassa fever; plague; poliomyelitis; Q fever; rabies; smallpox; trichinosis; tularemia; typhoid; typhus; Weil's disease; yellow fever	

Arrow Books Limited
17-21 Conway Street, London W1P 6JD
An imprint of the Hutchinson Publishing Group
London Melbourne Sydney Auckland Johannesburg
and agencies throughout the world

First published 1980
Reprinted 1980
New edition 1985
©Barry Popkess 1980, 1985

This book is sold subject to the condition that it shall not, by way of trade or otherwise, be lent, resold, hired out, or otherwise circulated without the publisher's prior consent in any form of binding or cover other than that in which it is published and without a similar condition including this condition being imposed on the subsequent purchaser

Set in Linotron Baskerville by
Book Economy Services (UK)
Crawley, Sussex

Printed in Great Britain by
Guernsey Press Co. Ltd.,
Guernsey, C.I.

ISBN 0 09 940110 X

412
~~359~~

Бомба типа "He" (High explosive).

В июле-месяце этого года ожидается производство первого взрыва атомной бомбы.

Конструкция бомбы. Активным веществом этой бомбы является элемент 94 без применения урана-235. В центре шара из плутония весом 5 килограмм помещается так наз. инициатор - бериллиево-полониевый источник альфа-частиц. Плутоний окружается 50 фунтами тьюб-аллой^{х)}, который является "темпером". Все это помещается в оболочку из алюминия толщиной 11 см. Эта алюминиевая оболочка, в свою очередь, окружается слоем взрывчатого вещества "пенталит" или "composition C" (по другим данным "composition B") с толщиной стенки 46 см. Корпус бомбы, в который помещается это ВВ, имеет внутренний диаметр 140 см. Общий вес бомбы включая пенталит, корпус и проч - около 3 тонн.

Ожидается, что сила взрыва бомбы будет равна силе взрыва 5.000 тонн ТНТ. (Коэффициент полезного действия - 5-6%). Количество "fission" равно $75 \cdot 10^{24}$.

Запасы активного материала.

- а) Уран-235. На апрель с/г было добыто 25 килограмм Уран-235. Его добыча в настоящее время составляет 7,5 кг. в месяц. Получение его
- б) Плутоний (элемент 94). В ливере-2 имеется 6,5 кг. плутония. Получение его налажено, план добычи перевыполняется.

х) тьюб-аллой - условное название урана (commercial radium tube)
↓
неизвестно какой - природного, 235 или обогащенной ка диг. уф-ка.

Ориентировочно взрыв ожидается 10 июля с/г.

Примечания: Составка составлена для устной ориентировки ак. Курганова

Записка Я.Б. Зельдовича и А.Д. Сахарова Ю.Б. Харитону
«Об использовании изделия для целей обжартия сверхизделия РДС-6С»

Zeldovich & Sakharov 14 января 1954 г.
Сов. секретно
14 Jan 1954, Secret (Особой важности)

АТОМНЫЙ ПРОЕКТ СССР

Документы и материалы

Под общей редакцией Л.Д. Рябева

Том III
Водородная бомба
1945—1956
Книга 2

Составители:

Г.А. Гончаров (отв. составитель), П.П. Максименко



Наука • Физматлит

Москва — Саров
2009




Отчет А.Д. Сахарова и Д.А. Франк-Каменецкого «Атомное обжартие»

9 декабря 1954 г.
Сов. секретно
(Особая папка)
Экз. № 1
A.D. Sakharov and D.A. Frank-Kamenetsky, "Atomic Compression", 9 Dec 1954, Secret

I. Принцип действия

Система атомного обжартия (сокращенно АО) состоит из следующих основных элементов конструкции (см. схему 1).

neutron filter
испаритель, фильтр



fission stage

thermonuclear stage

Схема №1

(...)

Применяя атомное обжартие, принципиально возможно сжать десятки и даже сотни кг легкого вещества внутри тяжелой оболочки до плотности, в десятки раз превосходящей его начальную плотность, что позволяет вызвать в легком веществе термоядерный взрыв с высоким коэффициентом использования.

(...)
Density compression factor of 10 is possible

III. Ожидаемые конструктивные элементы

По предварительным оценкам принципиально возможно создание системы АО со следующими ориентировочными характеристиками. Общий вес около 15 тонн. **Mass of proposed bomb = 15 tons**

(...)

При сгорании легкого вещества на (...) % выделяется энергия, равная 7,5 мегатонн ТЭ

(...)
Yield of proposed [15 ton] bomb = 7.5 Mt

Создание технически совершенной системы АО в габарите, существенно меньшем 15 тонн, вероятно, является более сложной, но тоже выполнимой задачей.

Созданию технически совершенной системы АО в габарите 15 тонн должен предшествовать опыт с более примитивной системой, проверяющий основные физические принципы АО и не требующий для своей подготовки длительной теоретической работы.


Записка Я.Б. Зельдовича и А.Д. Сахарова Ю.Б. Харитону
«Об использовании изделия для целей обжартия сверхизделия РДС-6С»

14 января 1954 г.
Сов. секретно
(Особой важности)
Zeldovich & Sakharov

Товарищу Харитону Ю.Б.

В настоящей записке сообщаются предварительная схема устройства для АО² сверхизделия и оценочные расчеты ее действия. Применение АО было предложено В.А. Давиденко.

Proposed by V.A. Davidenko



Boron filling

Предлагаемая система состоит из металлического корпуса (...), разделенного диафрагмой Д на два приблизительно равных объема. Общий вес конструкции около 26—30 тонн.

(...)

В одном объеме находится изделие А³, в другом — изделие С⁴. Изделия А и С окружены борной заливкой.

(...)
(Boron filling)

Первый период — распространение энергии по изделию А — не рассматриваем; в этом периоде вначале энергия более чем наполовину представляет собой энергию излучения и распространяется по механизму чистой теплопроводности, однако к концу периода уже вырабатывается ударная волна, скорость которой становится больше скорости диффузии излучения.

(...)

Boron converts x-rays from fission stage A into shock wave, compressing thermonuclear stage

Исполнено от руки в 1 экз. на 16 листах.

Исп. Зельдович Я.Б. и Сахаров А.Д.

Дело № 4. 14/1. А. Сахаров

Маш. 9/10 оп

14/1 54 г.

Архив ВНИИЭФ. Ф. 1, оп. 3с, ел. кр. 35, л. 7—52. Руккопись Я.Б. Зельдовича и А.Д. Сахарова. Подлинник.

Препроводительная записка Е. П. Славского в Президиум ЦК КПСС с представлением сообщения по результатам испытания изделия РДС-37

Secret 24 Nov. 1955 report by E. P. Slavsky to the Presidium of the USSR on results of 1.6Mt RDS-37 test
24 ноября 1955 г.
Сов. секретно
(Особой важности)

В Президиум ЦК КПСС

Представляю подробное сообщение т. Завенягина и других по результатам испытания изделия РДС-37, полученное 23 ноября 1955 года.

Приложение: рукописный материал мб. ст.-1191оп на 4 листах.

п/п Е. Славский

24 ноября 1955 г.
исх. ст.-1398/1

[Приложение]

В Президиум ЦК КПСС

22 ноября 1955 г. в 9 часов 47 минут по местному времени на полигоне № 2 Министерства обороны СССР произведено испытание экспериментальной водородной бомбы новой конструкции — РДС-37.

Испытание проводилось путем сбрасывания бомбы с самолета Ту-16 с высоты 12 тыс. метров.

Бомба сбрасывалась с парашютом, что дало возможность увеличить время ее падения с 55 до 71 секунды и уйти самолету на безопасное расстояние.

В день испытаний была облачная погода, высота нижней кромки облаков была более двух километров.

Взрыв произошел на высоте 1 550 метров, и благодаря этому огненный шар хорошо наблюдался, пока не поднялся за облака.

Самолеты полностью разрушены на расстоянии до 5 000 метров, танки сильно повреждены на расстоянии до 2 000 метров, артиллерия получила полные разрушения на расстоянии до 3 000 метров.

On 22 Nov. 1955 at 9.47am an RDS-37 was dropped by a Tu-16 flying at 12km altitude.

Parachute delivery gave time for the plane to escape to a safe distance before detonation.

Detonation occurred at 1.55km altitude. Severe damage occurred out to 5 km for planes, 2 km for tanks and 3 km for field artillery.

Постановление СМ СССР № 46-31сс

о результатах испытания изделия РДС-27 и РДС-37, серийном производстве изделия РДС-27, разработке и изготовлении изделий на принципе атомного обжигания¹

5 Jan. 1956
5 января 1956 г.
Особой важности

USSR Council of Ministers on RDS27 & RDS37

Совет Министров СССР отмечает, что проведенное испытание изделия РДС-27 и основанного на принципе АО изделия РДС-37 дало положительные результаты и открывает возможность значительного увеличения мощности изделий при одновременном сокращении расхода атомных взрывчатых веществ.

Совет Министров СССР ПОСТАНОВЛЯЕТ:

1. Обязать Министерство среднего машиностроения:

а) приступить к изготовлению изделий, основанных на принципе АО, и изготовить в 1956 г. 10 изделий мощностью 1,7–1,9 млн т и 10 изделий мощностью 0,5 млн т. В 1956 г. подготовить производство на выпуск в течение 1956–1960 гг. в несколько раз больше мощных изделий, чем намечалось ранее;

Orders: 10 bombs of 1.7-1.9Mt yield and 10 bombs of 0.5 Mt yield stockpiled for 1956.

б) организовать в 1956 г. серийное изготовление изделий РДС-27;

Order: manufacture (serial production) RDS27

в) разработать и изготовить изделие на принципе АО мощностью 20–30 млн т весом 20–26 т и подготовить испытание его в III кв. 1956 г. на Новой Земле с самолета М-4 с применением парашюта;

Order: make a 20-30 Mt bomb with a mass of 20-26 tons for air drop testing on Novaya Zemlya using an M-4 aircraft and a parachute.

Записка А. Д. Сахарова, Я. Б. Зельдовича и В. А. Давиденко Н. И. Павлову с оценкой параметров изделий

мощностью в 150 мегатонн и один миллиард тонн ТНТ
2 Feb. 1956 report by A. D. Sakharov, Ya. B. Zeldovich and V. A. Davidenko to N. I. Pavlov on 150 Mt and 1,000 Mt product designs
2 февраля 1956 г.
Сов. секретно
(Особая папка)
Экз. № ...

Option 1: Товарщцу Павлову Н. И.

Сообщаем оценку параметров изделия мощностью в 150 мегатонн ТНТ.
150Mt device using enriched lithium-6 fuel: вариант

Изделие с дейтеридом лития (...)[-ото] обогащения, по-видимому, может быть сделано в следующих габаритах: **4 metres diameter**

1) диаметр ~ 4 метра,

2) длина — 8–10 метров,

3) общий вес — около 100 тонн. **100 tons mass**

Option 2 (natural lithium deuteride)

Изделие с уменьшенным расходом лития-6 и с использованием природного лития может быть сделано в габаритах: **(Natural LiD containing 7.42% lithium-6)**

1) диаметр — 6–7 метров,

2) длина — 18–20 метров,

3) общий вес — около 500 тонн.

Изделие мощностью в один миллиард тонн ТНТ может быть изготовлено по любому из этих двух вариантов при увеличении весов дейтеридов и природного урана в 6–7 раз, а весов делящихся материалов — приблизительно в 3 раза.

Natural LiD fuelled 150Mt bomb is 6-7m diameter, 18-20 m long, and 500 tons in mass. To increase the total yield from 150 Mt to 1000 Mt in either option 1 or option 2 (highly enriched Li-6 D or natural LiD containing 7.42% Li-6), simply increase the LiD and U in thermonuclear charge by factor of 6-7, and fissile mass by 3 times

Comparison of U²³⁸(n,2n)U²³⁷ production by 14.1 MeV neutrons in 1953 Russian and 1954 USA tests




Page 326:

Таблица относительных выходов

U-238 fission abundance:

ИЗОТОПЫ	Дата взрыва			RDS-6 (Russian)	U ²³⁸ На спектре деления
	Castle-Bravo 28.II 54 г.	Castle-Romeo 26.III 54 г.	Castle-Yankee 4.V 54 г.		
Zr ⁹⁵	0,37 ± 0,08	1,0 ± 0,1	1,15 ± 0,2	12.VIII 53 г.	0,82
U ²³⁷	0,9 ± 0,2	1,65	1,9 ± 0,2	4,6	—

NOTE: Zr-95 abundances are indicative of unfractionated fission products, since it is well known from American work that Zr-95 doesn't fractionate significantly, relative to U-237 in these Russian fallout samples.





America did not bother to expose houses to nuclear tests until 47 kt Easy in 1951.



Trench field fortifications and bomb tower

Building protected by earth-filled blast walls

Entire brick house exposed to RDS1 in 1949



Moscow type housing blocks exposed in 1949.



28 KT RDS-4 AIR BURST AT 600 M ALTITUDE, 1953





RUSSIAN 3.5 KT UNDERWATER TEST IN 1955



RUSSIAN 6 KT UNDERWATER TEST IN 1957



41.2 kt Russian 380m air burst Joe-3 / RDS-3 (composite Pu and U235 core), 18 October 1951



Chagan River 140kt Russian test

96% clean (4% fission) 140 kt Chagan River nuclear weapon cratering (earth penetrator based) test.

**Joe-4 (RDS-6) 400 kt Teller "alarm clock"-design H-bomb
photo taken 15 seconds after detonation 12 August 1953**



TIER 10/6



Intelligence Memorandum

Office of Transnational Issues 30 August 2000

Evidence of Russian Development of New Subkiloton Nuclear Warheads [redacted]

(b) (1)
(b) (3)

СІА О П І Т І N 2000-011 X

public statements by Russian scientists and officials since 1993 indicate that the last nuclear warhead designed during the Soviet era was a device tailored for enhanced output of high-energy X-rays with a total yield of only 300 tons.

Judging from Russian writings since 1995 and Moscow's evolving nuclear doctrine, new roles are emerging for very-low-yield nuclear weapons—including weapons with tailored radiation output—and there are powerful advocates for development of such weapons in the country's military and weapons community. The Moscow press claimed that a draft presidential edict from Yel'tsin called for "development of new-generation nuclear weapons."

APPROVED FOR RELEASE
DATE: OCT 2005

- Recent statements on Russia's evolving nuclear weapons doctrine lower the threshold for first use of nuclear weapons and blur the boundary between nuclear and conventional warfare. Very-low-yield nuclear weapons reportedly could be used to head off a major conflict and avoid a full-scale nuclear war.

In the post-Soviet era, the need for subkiloton nuclear weapons with minimal long-term contamination has been argued in the media by senior Ministry of Atomic Energy (Minatom) officials, nuclear weapons scientists, and military academics since the mid-1990s. Advocates often claim to know that the United States is developing the next generation of nuclear weapons and argue that Russia must not lag behind. Somewhat inconsistently, they also cite clean, very-low-yield weapons as an "asymmetric response" to US superiority in conventional weapons. According to Sergei Rogachev, Deputy Director of the Arzamas-16 nuclear weapons design laboratory, "Russia views the tactical use of nuclear weapons as a viable alternative to advanced conventional weapons."

- Senior Russian military officers have advocated the use of highly-accurate, super-low-yield nuclear weapons in Russian military journals such as *Military Thought* and *Armeyskiy Sbornik*. Deputy Commander in Chief of the Strategic Rocket Forces Muravyev stated that to have an effective impact across the entire spectrum of targets, strategic missile systems should be capable of conducting surgical strikes in a wide spectrum of ranges with minimal ecological consequences, which could be achieved with low-yield nuclear weapons.

Soviet Era Development of Tailored - Output Nuclear Devices [redacted]

Russian development of nuclear devices tailored to enhance certain types of radiation output began during the Soviet period when "clean" nuclear devices—that is with reduced contamination from fission products—were needed for peaceful nuclear explosions (PNE's), according to statements by the developers. Clean PNE devices were in effect the first enhanced-radiation devices produced in Russia and likely precursors of tailored-output devices developed later for both effects testing and weapons development, which involved the same scientists (see appendix B for detailed discussion).

Enhanced-radiation weapons are designed to increase the effective range of gamma, neutron, X-ray, or electromagnetic pulse effects beyond the range of the airblast and fireball effects. Clean PNE devices are designed to minimize contamination from fission products by maximizing the fraction of the total yield produced by fusion. The two objectives are achieved by similar design approaches. [redacted]

Former Atomic Energy Minister Mikhaylov, other nuclear scientists, military officers, and national security commentators have described these new weapons as blurring the boundaries between conventional and nuclear war. In a 1996 treatise, Mikhaylov advocated developing a new generation of nuclear battlefield arms with relatively low yields that would change the perception of nuclear arms as weapons of mass destruction. In 1999, he claimed that these new-generation nuclear charges would sharply lower the psychological threshold of nuclear weapons use and would increase the likelihood of a nuclear strike in a local conflict, according to an independent Russian military newspaper.

- The development of low-yield warheads that could be used on high-precision weapon systems would be consistent with Russia's increasing reliance on nuclear weapons to deter conventional as well as nuclear attacks, especially given widespread perceptions of a heightened threat from NATO and the reduced capabilities of Russian conventional forces. Russia has no prospect of restoring its conventional military capabilities in the foreseeable future, nor of matching the West in the procurement and deployment of advanced weapon systems that can be brought to bear at the nonnuclear level.

The possible diverse applications for subkiloton nuclear weapons devices range from tactical battlefield weapons to antisatellite weapons. Media reports have noted that current modernization plans will affect Russia's entire stockpile, from tactical to strategic weapons. According to the December 1999 issue of the Army Journal *Armeyskiy Sbornik*:

"For an effective impact across the entire spectrum of targets, strategic missile systems should be capable of conducting 'surgical' strikes over a wide spectrum of ranges in the shortest period of time with minimal ecological consequences. This is achieved by using highly accurate, super-low-yield nuclear weapons, as well as conventional ones, and requires the highest accuracy."

The range of applications will ultimately be determined by Russia's evolving nuclear doctrine, and could include artillery, air-to-air missiles, ABM weapons, anti-satellite weapons, or multiple rocket launchers against tanks or massed troops. [redacted]

NOTE: the last Russian nuclear weapon test in Ukraine was on 16 September 1979, "coincidentally" the same 0.3 kiloton (300 tons of TNT) yield as the new Russian battlefield tactical nuclear warheads! Because of the atmospheric nuclear test ban at that time, it was set off 900m below ground in the Ukrainian coal mine at Yunkom in Donetsk as a "safety precaution" allegedly to release methane gas! This mine "resumed normal operations" the next day.

Russia's Evolving Nuclear Doctrine [redacted]

Since the dissolution of the USSR in 1991, Moscow's military doctrine has undergone a major shift with respect to the possible use of nuclear weapons. The deterioration of Russia's conventional military capabilities led to the adoption of a broadened concept of nuclear deterrence as early as the fall of 1992. Russia's nuclear arsenal was invoked to deter any large-scale conventional aggression in addition to nuclear attacks. [redacted]

This concept in turn necessitated a rethinking of the old Soviet pledge—initially endorsed by President Yel'tsin—that Moscow would never be the first to use nuclear weapons. A November 1993 statement of *Basic Provisions of the Military Doctrine of the Russian Federation* clearly departed from the decade-old pledge never to be the first to use nuclear weapons and adopted a broadened concept of nuclear deterrence covering large-scale, nonnuclear threats to Russia. As a warning to potential adversaries, Moscow indicated it might use nuclear weapons first if an aggressor takes actions to destroy or disrupt operation of Russia's strategic nuclear forces, missile attack warning system, or nuclear and chemical industries. [redacted]

ГРАЖДАНСКАЯ ОБОРОНА

Учебник

2014 г.

Защитными свойствами от действия ударной волны обладают также танки, БТР и БМП.

При невозможности использовать защитные свойства различных сооружений следует применять элементарные меры защиты. Так как для незащищенного человека наибольшую опасность представляет скоростной напор, то целесообразно до подхода ударной волны лечь на землю лицом вниз, головой или ногами в сторону взрыва. При этом площадь поперечного сечения уменьшается примерно в 10 раз, а воздействие скоростного напора будет минимальным.

Воздействие скоростного напора снижают различные углубления (кюветы, ямы, воронки и др.) или невысокие прочные стенки, пни и другие предметы, за которыми можно укрыться.




Рис. 1.8. Защитные свойства полевых фортификационных сооружений от воздушной ударной волны ядерного взрыва

CIVIL DEFENSE

Textbook

2014 г.

Tanks, armored personnel carriers also have protective properties against the action of a shock wave and BMP.

If it is impossible to use the protective properties of various structures, elementary protective measures should be applied. Since high-speed pressure is the greatest danger for an unprotected person, it is advisable to lie on the ground face down, head or feet in the direction of the explosion before the shock wave approaches. At the same time, the cross-sectional area is reduced by about 10 times, and the impact of the high-speed pressure will be minimal.

The impact of high-speed pressure is reduced by various depressions (ditches, pits, funnels, etc.) or low strong walls, stumps and other objects behind which you can hide.




Figure 1.8. Protective properties of field fortifications from the air shock wave of a nuclear explosion

January 22, 1979

The Honorable William Proxmire
Chairman, Senate Banking Committee
United States Senate
Washington, D.C.

Dear Senator Proxmire:

Your request in recent hearings for an explanation of the discrepancy between our estimates and ACDA's estimates of Soviet losses in a nuclear war is clearly important and warrants a clear and candid answer. Unfortunately, Mr. Spurgeon Keeny, the Deputy Director of ACDA, chose to incorrectly represent our work. I appreciate the opportunity to set the record straight and to point out what we have determined to be the factors contributing significantly to the differences between the two estimates.

Population Protection

In his attempt to discredit our work, Mr. Keeny incorrectly inferred that this work was based on mere "assumptions" and "simple ratios." In fact, our approach was to analytically duplicate the provisions of the Soviet Union's civil defense plans and preparations. This effort was supported by extensive research into Soviet literature, use of rigorous system engineering functional analysis techniques, and a program of testing to establish the effectiveness of Soviet shelters and industrial protection methods. Moreover, the impact of uncertainties and possible imperfections in Soviet execution of their plans were examined parametrically.

Mr. Keeny's statement that we "assumed there would be no casualties from fallout" is false. The record of hearings before the Joint Committee on Defense Production (November 17, 1976) clearly shows that the data presented counted as fatalities all persons receiving a radiation dose of 200 rads or more. Moreover, our more recent studies of which ACDA is aware have treated this value parametrically.

By protecting their people against fallout, the Soviets can substantially limit their population fatalities. Figure 1 shows that even very rudimentary protection, such as basements or expedient shelters, is sufficient to minimize fatalities. In the ACDA analysis, the majority of the evacuees were assumed to have a protection factor of 10 or less, which results in enormously high fatalities compared to what the Soviets could achieve if they carry out even the most modest of the measures outlined in their plans and literature.

Assumption Variables Versus U.S.S.R. Civil Defense Effectiveness Degree of Fallout Protection for Evacuees and Rural Population

BOEING




FIGURE 1

Mr. Keeny has incorrectly characterized our treatment of blast protection. In their cities, the Soviets are building industrial shelters and apartment basement shelters with a blast resistance of at least 150 psi and 60 psi, respectively. These ratings were calculated for the Defense Nuclear Agency based on knowledge of construction details such as beam dimensions, concrete quality, and structural reinforcement size and placement. The Soviet designs for expedient shelters have been built and exten-

Assumption Variables Versus U.S.S.R. Civil Defense Effectiveness

Distance Evacuated




FIGURE 2

Assumption Variables Versus U.S.S.R. Civil Defense Effectiveness

Blast Protection Provided Evacuees and Rural Population




FIGURE 3

As to the reasons why our results differ from those produced by ACDA: ACDA assumed that 30 percent of the Soviet urban population would not be evacuated but that the good quality shelters would accommodate only 10 percent. Thus, 20 percent of the Soviet urban population was assumed unevacuated and inadequately protected, which of course subjects them to massive losses. The Soviet plans, which we endeavored to represent in our analysis, indicates that urban residents not sheltered will be evacuated.

A second difference centers around the way in which the Soviets choose to distribute and provide blast protection for their evacuees. The ACDA analysis assumed that the Soviets would cluster their evacuees in hosting areas, which we estimate could result in some concentrations as high as 500 persons per square mile. The evacuees were assumed to have no blast protection, so fatalities would occur at 3 to 7 psi according to the source used by ACDA. Figure 3 shows that a distribution of 500 persons per square mile and 3 psi fatal blast level results in a fatality level almost 100 times greater than a uniform distribution and blast protection to 15 psi (the minimum provided by Soviet expedient shelters). It is important to remember that it is the Soviet Union and not the United States that controls such factors as evacuation, distribution, and sheltering of the Soviet citizens.

The ACDA study of industrial protection, which I have reviewed, is not a competent work. The hardness levels known to be achievable on industrial components are seriously understated while the difficulty of achieving these levels is overstated. The resiliency of industry in recovering from damage is disregarded. The report's fixation on the capability of one-megaton weapons to damage industry is misleading since the U.S. would be able to deliver few of these weapons against Soviet targets. Moreover, the ACDA study fails to assess the impact of protection on the survival and recovery of the Soviet industrial base as a whole.


T. K. Jones

BOEING

Extract from TK Jones' 1979 debunking of disarmament liars.



Nazi liar:

We, the German Führer and Chancellor and the British Prime Minister, have had a further meeting today and are agreed in recognising that the question of Anglo-German relations is of the first importance for the two countries and for Europe.

We regard the agreement signed last night and the Anglo-German Naval Agreement as symbolic of the desire of our two peoples never to go to war with one another again.

We are resolved that the method of consultation shall be the method adopted to deal with any other questions that may concern our two countries, and we are determined to continue our efforts to remove possible sources of difference and thus to contribute to assure the peace of Europe.

Handwritten initials and signature.

Neville Chamberlain

September 30, 1938.



SECRETARY OF DEFENSE
1000 DEFENSE PENTAGON
WASHINGTON, DC 20301-1000

6/3/2018

The Honorable Mitch McConnell
Majority Leader
United States Senate
Washington, DC 20510

Dear Senator McConnell,

You recently received a letter from several former government officials regarding the President's request to lower the nuclear explosive yield of a small number of existing submarine launched ballistic missile warheads (W76-2). As you know, the President requested this modest adjustment to our nuclear capabilities to counter Russia's apparent belief that it could use its low yield nuclear weapons to coerce the North Atlantic Treaty Organization or otherwise support conventional aggression against U.S. allies and partners.

Critics of this approach argue that current U.S. nuclear forces and nuclear doctrine can counter Russia's limited nuclear use doctrine and tactical nuclear weapons. It is not possible to determine precisely what is needed to deter with high confidence. It is, however, possible to get indications that one's deterrence strategy, posture, and capabilities are potentially inadequate. Since the 2010 Nuclear Posture Review (NPR), Russia has increased the number and diversity of its nuclear capabilities, continues to practice and exercise with these forces, and has issued veiled nuclear threats against the United States, its allies, and partners. This suggests that Russia is seeking ways to use nuclear weapons in support of its national security policy, and it suggests that measures by the previous Administration to modernize our nuclear forces may not be sufficient to deter Russian aggression. North Korea has made similar, coercive nuclear threats.

Particularly in the case of Russia, although it is true that the United States already has low-yield capable nuclear weapons, these weapons must be delivered by aircraft, which are vulnerable to formidable existing Russian air defenses. Russia may conclude that it can blunt the current U.S. low-yield response and that the United States would be self-deterred from using strategic nuclear weapons; the W76-2 low-yield warhead dispels this notion - however mistaken it might be.

(Also, low-yield option of B61 has insignificant neutron output!)

The authors of the letter argue that nuclear war cannot be controlled, and that there is no such thing as a limited nuclear war. Unfortunately, potential adversaries have openly discussed the benefits of limited nuclear employment. Therefore, effective U.S. deterrence requires ensuring that potential adversaries do not miscalculate regarding the consequences of nuclear first use, either regionally or against the United States itself. They must understand that there are no possible benefits from non-nuclear aggression or limited nuclear escalation. The W76-2 warhead is meant to reinforce the credibility of our response, which strengthens deterrence by denying potential adversaries the advantages they appear to believe they could realize from nuclear first use. It sends a signal to Russia and other potential adversaries that, in the words of



the authors of the letter, "the United States is serious about maintaining an unambiguously strong nuclear deterrent."

Finally, we get to the crux of the authors' argument, which is "that the president might feel less restrained about using it in a crisis." Let me be clear, any decision to employ nuclear weapons would be the most difficult decision a President has to make. This Administration, like the ones before it, has said that nuclear weapons would be employed only in extreme circumstances to protect our vital interests and those of our allies and partners. The W76-2 strengthens deterrence by raising the threshold to nuclear employment.

The 2018 NPR has received broad bipartisan support. The modernization of U.S. nuclear forces was begun by the previous Administration and will continue over the next twenty years. The President's request for the W76-2, a supplemental capability, is in response to developments in Russian nuclear doctrine, exercises, and its new nuclear capabilities. While strengthening the deterrence of attacks against the U.S., allies, and partners, it does not require developing a new nuclear warhead or nuclear testing, it does not violate any nuclear arms control treaty, and it does not increase the size of the nuclear stockpile.

Nuclear modernization is affordable and is the number one priority of the Department of Defense. Thank you for your continued support.

Sincerely,

**(US DEFENCE SEC.
MATTIS)**


The 1990 revised secret Capabilities of Nuclear Weapons DNA-EM-1 gives initial radiation data for 13 designs in the 1984 edition, showing neutron doses at 1 km ground range from a surface burst on ordinary soil in unobstructed open terrain of only 0.666 rads/kiloton for nuclear warhead type 10 (the low-yield dial-a-yield option for a B61 strategic bomb which has multiple yield options), compared to 1,660 rads/kiloton for warhead type 13 (the tactical neutron weapon W79).

This is because the thicker outer casing on a B61 weapon with high yield options absorbs most of the neutrons from the primary stage, and thereby shows that you cannot simply use the low-yield option on a B61 as a replacement for tactical nuclear weapons like neutron bombs.

President Trump's US Secretary of Defense defending low yield tactical nuclear weapons against President Putin's threats to invade other countries and to use nuclear coercion threats of escalating a conventional war to induce appeasement

FIGURE 2

**Size of the U.S. Nuclear Weapons Stockpile, 1945–2020
(OR, WHY PUTIN FEELS CONFIDENT INVADING UKRAINE JUST AS HITLER INVADDED HIS NEIGHBOURS WHILE PACIFISTS DISARMED THE UK UNTIL 1935 THEN REARMED SLOWER THAN THE NAZIS, TO AVOID PROVOKING A SECOND WORLD WAR BY WINNING AN ARMS RACE.)**



SOURCE: U.S. Department of Energy, October 2021b.

NOTE: The figure depicts active and inactive warheads. Approximately 2,000 additional nuclear warheads are retired and awaiting dismantlement.

DIAGRAM ABOVE IS FROM FRANK G. KLOTZ AND ALEXANDRA T. EVANS, MODERNIZING THE U.S. NUCLEAR TRIAD, RAND CORP., 2022, document: PE-A1434-1, 2022
<https://www.rand.org/pubs/perspectives/PEA1434-1.html>

**ANNUAL NATIONAL DEFENCE EXPENDITURES
(millions of dollars)**

Country	1933	1934	1935	1936	1937	1938	1939
Britain	455	480	595	846	1263	1693	1817
Germany	253	299	381	2600	3600	4000	4400

Source: J. F. Kennedy, *Why England Slept*, Sidgwick & Jackson, London, 1962, p. 184.

"If we handle Hitler right, my belief is that he will become gradually more pacific. ... I would feel confident if it were not for ... alarmists by profession and Jews." - Sir Neville Henderson, racist British Ambassador to Berlin, February 1939 telegram to the British Foreign Secretary.

"Hitler has gone straight off the deep end again ... What distresses me more than anything else is the handle which it will give to the critics ..." - Sir Neville Henderson, racist British Ambassador to Berlin, telegram to the British Foreign Secretary, 15 March 1939.

SOURCE: H.M.S.O., Documents on British Foreign Policy, 1919-1939, London, 1949, Third Series, IV, pages 593 and 595.

"At no time did Hitler threaten to initiate war against France and England. He simply threatened to 'retaliate' if they attacked him. The Munich crisis had an incredible sequel in March 1939. ... Hitler occupied the rest of Czechoslovakia. The technique he used is such an obvious prototype for a future aggressor armed with H-bombs that it is of extreme value to all who are concerned with the problem of maintaining a peaceful and secure world ..." - Herman Kahn, On Thermonuclear War, Princeton University Press, 1960, p. 403. (Putin's technique today!)

"... before World War II, for example, many of the staffs engaged in estimating the effects of bombing over-estimated by large amounts. This was one of the main reasons that at the Munich Conference and earlier occasions the British and the French chose appeasement to standing firm or fighting. Incidentally, these staff calculations were more lurid than the worst imaginations of fiction." - Herman Kahn, testimony to the 1959 hearings on the Biological and Environmental Effects of Nuclear War, page 883.

"As late as 1934, after Hitler had been in power for almost a year and a half, [British Prime Minister] Ramsey MacDonald still continued to urge the French that they should disarm themselves by reducing their army by 50 per cent, and their air force by 75 per cent. In effect, MacDonald and his supporters urged one of the least aggressive nations in Europe to disarm itself to a level equal with their potential attackers, the Germans [exactly what the pacifists did when getting Ukraine to disarm its nuclear deterrent 30 years ago!] ... Probably as much as any other single group I think that these men of good will can be charged with causing World War II. [Emphasis by Herman Kahn.]" - Herman Kahn, On Thermonuclear War, Princeton University Press, 1960, pp. 390-391.

"There is no security in armaments and we shall be no party to piling them up."

- Labour Party Leader of the British House of Commons Opposition, Clement Attlee, 1935 (two years after Hitler took power and began rearming Germany; quotation from Gilbert and Gott, The Appeasers, 1967).

Troubled by the failure of unilateral disarmament to save millions of lives in WWII, Attlee 12 years later as Prime Minister secretly ordered the stockpiling of the first British nuclear weapons to deter WWII from starting.

"How horrible, fantastic, incredible it is that we should be digging trenches and trying on gas-masks here because of a quarrel in a far away country between people of whom we know nothing."

- British Prime Minister Chamberlain, radio broadcast, 27 September 1938.

"Supposing I had gone to the country and said that Germany was rearming and that we must rearm ... I cannot think of anything that would have made the loss of the election from my point of view more certain."

- Prime Minister Stanley "the bomber will always get through" Baldwin (speech in House of Commons, 12 November 1936; his fans simply lied that he was referring to earlier non-existent elections than the 1935 one!).